HOTSPOT TRAINING MANUAL Health Physics Codes for the PC





DISCLAIMER

This document was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial products, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government thereof, and shall not be used for advertising or product endorsement purposes.

Work performed under the auspices of the U.S. Department of Energy by Lawrence Livermore National Laboratory under Contract W-7405-Eng-48.

The examples in this manual are excerpted from UCRL-MA-106315.

Steve Homann, Hazards Control Department, Lawrence Livermore National Laboratory.

Darvin Vauldonn Wilson, Technical Information Department, Lawrence Livermore Laboratory

HOTSPOT Training Manual

Health Physics Codes for the PC

Steve Homann

Darvin Vauldonn Wilson

February 1995

LAWRENCE LIVERMORE NATIONAL LABORATORY University of California • Livermore California • 94551



HOTSPOT HEALTH PHYSICS CODES

CONTENTS

| Lesson 1 HOTSPOT Health Physics Codes Overview | 1-1 |
|--|------|
| Lesson Objectives | 1-1 |
| HOTSPOT Functions | 1-3 |
| HOTSPOT Applications | 1-5 |
| Output Options | 1-7 |
| Models/Principles | 1-9 |
| Equations | 1-11 |
| Terminology Used to Describe | |
| HOTSPOT Output | 1-13 |
| Materials and Course Logistics | 1-15 |
| Computer System | 1-17 |
| Keyboard | 1-19 |
| Logging-on and Starting HOTSPOT | 1-21 |
| Monitors | 1-23 |
| HOTSPOT Library | 1-25 |
| HOTSPOT Main Menu and SETUP | 1-27 |
| Codes A–T | 1-29 |
| QUIT (Q Key) | 1-31 |
| Lesson 2 | |
| Plutonium Explosion | 2-1 |
| Lesson Objectives | 2-1 |
| Graphical Output and Assumptions | 2-3 |
| Code Description: Plutonium Explosion | 2-5 |
| Demonstration: Plutonium Explosion | 2-7 |
| Exercise: Plutonium Explosion | 2-23 |

Lesson 3

| Plutonium Fire | 3-1 |
|--|----------------------------------|
| Lesson Objectives Graphical Output and Assumptions Code Description: Plutonium Fire Demonstration: Plutonium Fire Exercise: Plutonium Fire | 3-1 3-3 3-5 3-7 3-25 |
| Lesson 4 | |
| Plutonium Resuspension | 4 -1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: Plutonium Resuspension Demonstration: Plutonium Resuspension Exercise: Plutonium Resuspension | 4-1 4-3 4-5 4-7 4-23 |
| Lesson 5 Uranium Explosion | 5- 1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: Uranium Explosion Demonstration: Uranium Explosion Exercise: Uranium Explosion | 5-1 5-3 5-5 5-7 5-23 |
| Lesson 6 | |
| Uranium Fire | 6-1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: Uranium Fire Demonstration: Uranium Fire Exercise: Uranium Fire | 6-1 6-3 6-5 6-7 6-23 |

| Lesson | 7 |
|--------|---|
|--------|---|

| Tritium Release | 7-1 |
|---|--|
| Lesson Objectives Graphical Output and Assumptions Code Description: Tritium Release Demonstration: Tritium Release Exercise: Tritium Release | 7-1 7-3 7-5 7-7 7-21 |
| Lesson 8 | |
| Nuclear Explosion | 8-1 |
| Lesson Objectives Assumptions—Nuclear Explosion Example: Nuclear Explosion Code Description: Nuclear Explosion Demonstration: Nuclear Explosion Exercise: Nuclear Explosion | 8-1 8-3 8-8 8-9 8-11 8-15 |
| Lesson 9 | |
| General Plume | 9-1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: General Plume Demonstration: General Plume Exercise: General Plume | 9-1 9-3 9-5 9-7 9-25 |
| Lesson 10 | |
| General Explosion | 10-1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: General Explosion Demonstration: General Explosion Exercise: General Explosion | 10-1 10-3 10-5 10-7 10-25 |

| Lesson 11 | |
|--|-------------------------------|
| General Fire | 11-1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: General Fire Demonstration: General Fire Exercise: General Fire | 11-1 11-3 11-3 11-23 |
| Lesson 12 | |
| General Resuspension | 12-1 |
| Lesson Objectives Graphical Output and Assumptions Code Description: General Resuspension Demonstration: General Resuspension Exercise: General Resuspension | 12-1 12-3 12-3 12-23 |
| Lesson 13 | |
| Radionuclides in the Workplace | 13-1 |
| Lesson Objectives Graphical Output and Assumptions Demonstration: Radiation Workplace | 13-1 13-3 13-5 |
| Lesson 14 | |
| FIDLER Calibration | 14-1 |
| Lesson Objectives Graphical Output and Assumptions Demonstration: FIDLER Calibration | 14-1 14-3 14-75 |
| Lesson 15 | |

15-1

LUNG Screening

| Lesson Objectives Output and Assumptions Demonstration: LUNG Screening | 15-1 15-3 15-5 |
|---|--|
| Lesson 16 Output Options | 16-1 |
| Lesson Objectives Options Demonstration: Option C Options Demonstration: Option M Options Demonstration: Option Z Options Demonstration: Option D Options Demonstration: Option O Options Demonstration: Option I | 16-1 16-3 16-5 16-9 16-11 16-13 |

Appendix A: HOTSPOT Health Physics Codes for the PC User Manual

Lesson 1 HOTSPOT Health Physics Codes Overview

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 1 – HOTSPOT HEALTH PHYSICS CODES OVERVIEW

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to describe the

HOTSPOT Health Physics Codes program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the HOTSPOT program in terms of its capabilities, uses, system basics, general outputs, models and principles, HOTSPOT Library, terminology, formulas, and menus and their use
 - Identify the basic hardware and software required for running HOTSPOT
 - Describe the keyboard layout and basics of keyboard usage
 - Log-on and start HOTSPOT

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of HOTSPOT.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




1-#1

- Briefly define Atmospheric Dispersion Modeling and describe the HOTSPOT Health Physics Code Program (HOTSPOT).
- Have students read the Lesson Objectives on the Reference page.

Lesson Objectives

- At the end of this lesson, trainees will be able to:
 - Describe the HOTSPOT Health Physics Codes program (HOTSPOT)
 - Describe HOTSPOT capabilities, uses, system basics, general outputs, models and principles, HOTSPOT Library, terminology, formulas, and menus and their use
 - Identify the basic hardware and software required for running HOTSPOT
 - Describe the keyboard layout and basics of keyboard usage

HOTSPOT Functions




1-#2

- HOTSPOT provides a first-order approximation of the radiation effects of released materials.
- The codes are reasonably accurate and provide for consistent output.
- The use of HOTSPOT will help minimize the probability of errors in subsequent response actions.

HOTSPOT Functions

- HOTSPOT provides Health Physics personnel with a fast, field-portable calculational tool for evaluating accidents involving radioactive materials.
- HOTSPOT codes are a first-order approximation of the radiation effects associated with the atmospheric release of radioactive materials.
- HOTSPOT is reasonably accurate for a timely initial assessment.
- HOTSPOT codes produce a consistent output for the same input assumptions.
- HOTSPOT codes minimize the probability of errors associated with reading a graph incorrectly or scaling a universal nomogram during an emergency.

HOTSPOT Applications



1-#3

- HOTSPOT consists of four general programs: Plume, Explosion, Fire, and Resuspension.
- HOTSPOT also includes other material-specific programs: Plutonium, Uranium, and Tritium.
- HOTSPOT also has programs for Radiation in the Workplace, FIDLER Calibration, LUNG Screening, and Nuclear Explosion.

HOTSPOT Applications

| • | HOTSPOT | contains | four | general | programs: |
|---|---------|----------|------|---------|-----------|
|---|---------|----------|------|---------|-----------|

- Plume
- Explosion
- Fire
- Resuspension

These programs are used to calculate a downwind assessment following the release of radioactive material resulting from a continuous or puff release, explosive release, fuel fire, or an area contamination event.

- Other HOTSPOT programs are used to initially assess plutonium, uranium, and tritium releases:
 - Plutonium Explosion
 - Plutonium Fire
 - Plutonium Resuspension
 - Uranium Explosion
 - Uranium Fire
 - Tritium Release
- HOTSPOT also includes programs for the following:
 - Radiation in the Workplace
 - FIDLER Calibration
 - LUNG Screening
 - Nuclear Explosion

Output Options

 HOTSPOT provides, for screen, printer, disk file, and graphics, several output options:

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------------------------------------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |
| G: | GRAPHICS | Displays results in graphical format | | |

1-#4

- These options enable you to perform real-time assessments, as well as create images and files for reporting purposes.
- Explain Screen options (selection 1 or 2):
 - Type 1 for data output tables containing input values, maximum dose distance and maximum CEDE; press Enter for additional tables showing 50-year dose commitment.
 - Type 2 for data output tables where you enter an off-axis position.
- Explain the Printer options (selection 3 or 4): Typing 3 or 4 allows you to select the HOTSPOT printer.
- Explain the Disk File options (selection 5 or 6): Typing 5 or 6 allows you to enter the destination drive and filename by which to file the data output.
- Explain the Graphics options (selection G): They are CEDE contours, Ground Deposition Contours, Centerline 50-yr CEDE vs. Distance, and Centerline Ground Deposition vs Distance.

Output Options

- HOTSPOT provides output options for screen, printer, disk file and graphics; these options enable you to perform real-time assessments, as well as create images and files for reporting purposes:
 - Type 1 for data output tables containing input values, maximum dose distance and maximum CEDE; for example:

HOTSPOT 7.0 GENERAL PLUME HALFLIFE: 10.720 yr **RADIONUCLIDE: KR-85** Inhalation Class: N/A RELEASE FRACTION: 1.00E+00 2.0E+04 Ci SOURCE TERM: EFFECTIVE RELEASE HEIGHT: 10.00 m 0.000000 % FILTER EFFICIENCY: WIND SPEED (h=H-eff): 1.1 m/s WIND SPEED (h=2 m): 1.0 m/s **DEPOSITION VELOCITY:** 0.0E+00 cm/s STABILITY CLASS: Α INVERSION LAYER HEIGHT: 5000.0 m RECEPTOR HEIGHT: $0.0 \, m$ MAXIMUM DOSE DISTANCE: <0.1 km SAMPLE TIME 10.000 min >5.4E-03 rem MAXIMUM CEDE:

 Press Enter for additional tables showing 50-year dose commitment; for example:

PLUME CENTERLINE D= 0.10 km D= 0.20 km D= 0.50 km 1.1E+01 (Ci-s)/m^3 CHI = 3.2E+00 (Ci-s)/m^3 5.3E-01 (Ci-s)/m^3 CHI = CHI = **50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: EFFECTIVE EFFECTIVE EFFECTIVE** 1.00E+00 DOSE DOSE DOSE EQUIVALENT 5.4E-03 rem **EQUIVALENT** 1.5E-03 rem **EQUIVALENT** 2.5E-04 rem

Type 2 for data output tables where you enter an off-axis position.


Enter Distance, km, and push "Enter" To enter an off-axis position (x, Y), enter x y, e. g., 3 6 for x = 3 km and y = 6 km Push "Enter" w/o data entry to QUIT

- Typing 3 or 4 allows you to select the HOTSPOT printer.
- Typing 5 or 6 allows you to enter the destination drive and filename by which to file the data output; for example:

FILENAME . TXT C:\FILENAME . TXT B:\SUB\FILENAME . TXT B:\SPDSHEET . WQ1

 Graphics options (selection G): They are CEDE contours, Ground Deposition Contours, Centerline 50-yr CEDE vs. Distance, and Centerline Ground Deposition vs Distance.

Models/Principles



1-#5

- HOTSPOT codes are based on the Gaussian Plume Model.
- Have students read the Reference page for a discussion of the following:
 - Gaussian Plume Model
 - HOTSPOT algorithms
 - The dosimetric methods of ICRP Publication 30
 - Individual doses (unweighted); 50-year committed effective dose equivalent (CEDE)
 - Classic units (rem, rad, curie, and SI units)
 - Dose values (inhalation)
 - Noble gases
 - Specific dose conversion factors
 - Ground shine dose
 - Alpha-emitting radionuclides

Models/Principles

 HOTSPOT uses the well-established Gaussian Plume Model, widely used for an initial emergency assessment or safety analysis planning of a radionuclide release.

- Appendix B of the HOTSPOT Health Physcis Codes for the PC User Manual describes the HOTSPOT algorithms in detail.
- The dosimetric methods of ICRP Publication 30 were used throughout the HOTSPOT programs.
- Individual doses (unweighted) are produced, along with the 50-year committed effective dose equivalent (CEDE).
- HOTSPOT supports both the Classic units (such as rem, rad, curie) and SI units.
- HOTSPOT dose values are due solely to the inhalation of released material during the passage of the plume.
- In the specific case of noble gases, e.g., Kr-85, the submersion dose is output.
- The specific dose conversion factors for all of the radionuclides in the HOTSPOT Library can be viewed in the "HOTSPOT Library" program.
- The ground shine dose is not included because the effective dose equivalent (per hour of stay time in the contaminated area) due to ground shine is typically several orders of magnitude less than the CEDE due to plume passage.
- For alpha-emitting radionuclides (e.g., Pu-239, Am-241), the hourly ground-shine component is at least seven orders of magnitude less than the inhalation component.

Equations

The following Gaussian model equations are used to determine the atmospheric concentration of a gas or an aerosol.

$$C(x,y,z,H) = \frac{Q}{2\pi\sigma_y\sigma_z u} \exp\left[-\frac{1}{2}\left(\frac{y}{\sigma_y}\right)^2\right] \left\{ \exp\left[-\frac{1}{2}\left(\frac{z-H}{\sigma_z}\right)^2\right] + \exp\left[-\frac{1}{2}\left(\frac{z+H}{\sigma_z}\right)^2\right] \right\} \exp\left[-\frac{\lambda x}{u}\right]$$

If the inversion layer option is in effect, and s exceeds the inversion height L, the following equation is used. $\sigma_z \rangle L$:

$$C(x, y, z, H) = \frac{Q}{\sqrt{2\pi}\sigma_y L u} \exp \left[-\frac{1}{2} \left(\frac{y}{\sigma_y} \right)^2 \right] \exp \left[-\frac{\lambda x}{u} \right]$$

1-#6

- Have students refer to the HOTSPOT Health Physics Codes for the PC User Manual, Appendix B.
- Discuss the Gaussian Model Algorithms, Coordinate System, and Gaussian Equations.

Equations

 Refer to Appendix A the HOTSPOT Health Physics Codes for the PC User Manual, Appendix B for a discussion of Gaussian Model Algorithms, Coordinate System, and Gaussian Equations.

Terminology Used to Describe HOTSPOT Output

HOTSPOT
Health Physics Codes
for the PC
User Manual

Appendix C Glossary

1-#7


Notes:

 Have students read the HOTSPOT Health Physics Codes for the PC User Manual, Appendix C, the Glossary of HOTSPOT Output Definitions.

Terminology Used to Describe HOTSPOT Output

 Read the HOTSPOT Health Physics Codes for the PC User Manual, Appendix C, the Glossary of HOTSPOT Output Definitions.

Materials and Course Logistics



1-#8

- Course materials include a Training Manual and a User Manual.
- The course includes 16 lessons, is approximately 4 hours long, and includes in-class exercises.
- Your training consists of several resources:
 - Course instructor
 - Course manuals
 - HOTSPOT
 - List of references
 - Glossary of terms


Materials and Course Logistics

- The titles of the course manuals are as follows:
 - HOTSPOT Health Physics Codes for the PC by Steven G. Homann (User Manual)
 - HOTSPOT Health Physics Codes Training Manual: Atmospheric Dispersion Modeling Training Program by Darvin Wilson
- The titles of the course lessons are as follows:
 - Lesson 1: HOTSPOT Health Physics Codes Overview

This lesson provides an overview of the HOTSPOT Training Program course, the computer system, HOTSPOT (specifically the Main Menu, Setup, Codes A-T, the Quit key, and the HOTSPOT Library).

- Lesson 2: Plutonium Explosion (Code A)
- Lesson 3: Plutonium Fire (Code B)
- Lesson 4: Plutonium Resuspension (Code C)
- Lesson 5: Uranium Explosion (Code D)
- Lesson 6: Uranium Fire (Code E)
- Lesson 7: Tritium Release (Code T)
- Lesson 8: Nuclear Explosion (Code F)
- Lesson 9: General Plume (Code H)
- Lesson 10: General Explosion (Code I)
- Lesson 11: General Fire (Code N)
- Lesson 12: General Resuspension (Code J)
- Lesson 13: Radiation Workplace (Code G)
- Lesson 14: FIDLER Calibration (Code M)
- Lesson 15: LUNG Screening (Code M)
- Lesson 16: Output Options C, M, Z, D, O, and I

Computer System




1-#9

- Hardware—HOTSPOT runs on an IBM PC, XT, AT, or compatible computer.
- Software—The required software includes HOTSPOT Health Physics Codes 7.0 and the DOS operating system (version 3.0 or later version).
- Refer to system in class.

Computer System

- The hardware requirements for this course are as follows:
 - IBM PC, XT, AT, or compatible.
 - Minimum of 512 kbytes of RAM.
 - Single floppy disk drive (the programs run more efficiently when they reside on a hard disk).
 - The software supports either monochrome or color monitors (CGA, EGA, VGA).
 - Operating system = MS-DOS version 3.0 or later.
 - HOTSPOT supports high-resolution (300 dpi) output to printers, and also to graphics files (.PCX and .BMP Files).
- The required software is HOTSPOT Health Physics Codes 7.01 by Steven G. Homann.

Keyboard



1-#10


- Explain the following common features of the keyboard:
 - letter keys
 - shift keys
 - punctuation keys
 - spacebar
 - tab key
- Describe the keyboard's specialized keys:
 - function keys
 - numeric keys
 - arrow keys
 - ALT, CTRL, DEL, INS
 - Home
 - Enter
 - Page up, Page down
 - End
- Explain that the software in use determines the function of these keys.

Keyboard

 The keyboard is used for communicating with the computer. Using it, you can type instructions, commands, and information to be processed and stored.

- The keyboard used for inputting data into the HOTSPOT program is the standard QWERTY keyboard.
- Some features of the keyboard are like those of a typewriter: the letter keys, shift keys, punctuation keys, spacebar and tab key.
- The keyboard also contains some specialized keys: function keys, numeric keys, arrow keys, ALT, CTRL, DEL, INS, Home, Enter, Page up, Page down, Home, End. The software you are using determines what task each of these keys (or combination of keys) performs.
- Pressing the Enter key (or the Return key) allows you to enter information you have previously typed into the computer system.
- Use the Shift key together with any letter to make a capital letter.
- Use the Backspace, INS, and DEL to edit text you type.
- Page up, Page down, Home, and End keys are not used with HOTSPOT.

Logging-on and Starting HOTSPOT



1-#11

- Describe the start-up procedure when using HOTSPOT from a single disk drive system. (Refer to Reference page.)
- Describe the start-up procedure when starting HOTSPOT from a hard disk drive. (Refer to Reference page.)
- If equipment is available in the classroom, demonstrate both procedures or have students perform these procedures at their terminals.

Logging-on and Starting HOTSPOT

- Single disk drive system
 - To access the HOTSPOT program, first load the standard DOS operating system into your computer.
 - Put the "HOTSPOT" disk in the 'A' drive.
 - At the DOS prompt (i.e., A>), type "HOTSPOT" and push Return (Enter on some computers). The HOTSPOT main menu appears.
- Starting HOTSPOT from a hard disk system

1. Copy HOTSPOT files

If your have a hard disk, you will probably want to copy all of the HOTSPOT files onto it. The following instructions assume that you have DOS on your hard disk and that your hard disk is assigned to be drive "C."

- At the DOS prompt (C>), type MD\HOTSPOT and push Return. This
 creates a directory named HOTSPOT.
- Type CD\HOTSPOT and push Return. This makes HOTSPOT the current directory.
- Place the HOTSPOT program disk into drive A.
- Type COPY A;*.* and push Return. DOS then copies all of the files from the HOTSPOT disk to your hard disk in the current directory, HOTSPOT.

2. Start HOTSPOT

- Make sure the default drive letter at the DOS prompt is for the hard disk prompt, C>. If not, at the DOS prompt, type the letter of the hard disk and a colon. e.g., C: and push Return.
- If the current directory is HOTSPOT, proceed to the next step.
 Otherwise, you need to access the HOTSPOT directory. At the DOS prompt, type CD\HOTSPOT and push Return. This makes HOTSPOT the current directory.
- Type HOTSPOT and push Return. The HOTSPOT main menu appears.

Monitors

HOTSPOT SETUP PROCEDURE

This program configures your system PRINTER and MONITOR.

HOTSPOT will automatically adjust the screen output for most monochrome monitors. However, if the display is hard to read, you should select MONOCHROME from the following options. If the contour grids displayed on the concentration contours are not square, select Option R, and adjust the GRID RATIO.

ENTER A SELECTION

| М | : MONOCHROME | S : SCREEN RESOLUTION |
|---|---------------------|-----------------------|
| Р | : PRINTER/FILE | I : I/O PORT |
| С | : COLOR | R : CHANGE GRID RATIO |
| ٧ | : VIEW SETTINGS | U : UNITS |
| L | : SET PLOT CONTOURS | Q : QUIT |
| | | W : WIND HEIGHT |

1-#12

- HOTSPOT can be run with all IBM monitors (monochrome, CGA, EGA, VGA), although a monochrome monitor may require you to reconfigure HOTSPOT.
- The following settings can be changed:
 - M: Monochrome (Select M for a monochrome monitor.)
 - C: Color (Select C for a color monitor.)
 - S: Screen Resolution (Select S if the screen is hard to read. S = L or
 H. L is Low resolution; H is High resolution.)
 - R: Change Grid Ratio. (If the contour grids displayed on the concentration contours are not square, select Option R, and adjust the Grid Ratio.)

Reference

Monitors

- HOTSPOT will automatically adjust its output to most types of monochrome monitors, but some types of monochrome monitors will require that you configure HOTSPOT differently.
- If the monochrome display is difficult to read, you will need to change the monitor setting using the SETUP program.
- At the HOTSPOT main menu, select "S" for SETUP, and follow the prompted instructions.
- The following settings can be changed:
 - M: Monochrome (Select M for a monochrome monitor.)
 - C: Color (Select C for a color monitor.)
 - **S**: Screen Resolution (Select S if the screen is hard to read. **S** = **L** or
 - **H**. **L** is Low resolution; **H** is High resolution.)
 - R: Change Grid Ratio. (If the contour grids displayed on the concentration contours are not square, select Option R, and adjust the Grid Ratio.)

HOTSPOT Library

HOTSPOT RADIONUCLIDE LIBRARY

1: Look up a specific radionuclide

2: List all radionuclides

Q: Quit

1-#13

- If equipment is available in the classroom, demonstrate these procedures or have students perform these procedures at their terminals.
- Have students select L from the HOTSPOT Main Menu.
- Ask students to look up a specific radionuclide.
- Ask students to list all radionuclides.

HOTSPOT Library

- Step 1 Type L from the HOTSPOT Main Menu to select the HOTSPOT Library.
- Result The HOTSPOT Radionuclide Library Menu appears.
- Step 2 Type 1 to look up a specific nuclide.
- Step 3 Type in the name of a nuclide (for example, type KR-85).
- Result The following table appears:

| Nuclide Name | : | KR-85 |
|-------------------|---|---|
| Nuclide | : | KRYPTON |
| Atomic Number | : | 85 |
| Particle Class | : | N |
| HalfLife | : | 1.072E-01 years |
| Specific Activity | : | 3.9E+02 Ci / g |
| CEDE | : | 4.7E-04 (rem-m3) / (Ci-sec) Submersion |
| | | |

- Step 4 Push Return to continue.
- **Step 5** Type **2** to list all radionuclides in the library.

Press **Return** until you find the nuclide of interest.

 Result The Library displays the nuclide half-life and 50-yr CEDE conversion factor:

| NUCLIDE | HALF-LIFE | 50-YR CEDE CONVERSION FACTOR |
|---------|------------|--|
| KR-85 | 1.0720E+01 | 4.7E-04 (rem-m3) / (Ci-sec) SUBMERSION |

- Step 6 Press Return
- Result You return to the HOTSPOT Radionuclide Library Menu.
- Step 7 When finished, type Q to quit.

HOTSPOT Main Menu and SETUP

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

: Plutonium Explosion B: Plutonium Fire C: Plutonium Resuspension : Uranium Explosion E: Uranium Fire : Nuclear Explosion D : Radiation Workplace : General Explosion **H**: General Plume : General Resuspension K : Inhalation Dose : Tritium Release : HOTSPOT Library : FIDLER Calibration : General Fire and LUNG Screening

Q: QUIT

Enter Selection

1-#14

- Describe the various Main Menu choices.
- Describe the SETUP option and explain its purpose, which is to configure the system monitor and printer.

Reference

HOTSPOT Main Menu and SETUP

- The HOTSPOT Main menu contains HOTSPOT title box and S: Setup; Q: Quit; and A through T (for specific radioactive material and type of incident).
- If you select S (SETUP), the HOTSPOT SETUP PROCEDURE screen appears:

HOTSPOT SETUP PROCEDURE

This program configures your system PRINTER and MONITOR.

HOTSPOT will automatically adjust the screen output for most monochrome monitors. However, if the display is hard to read, you should select MONOCHROME from the following options. If the contour grids displayed on the concentration contours are not square, select Option R, and adjust the GRID RATIO.

ENTER A SELECTION

M : MONOCHROME S : SCREEN RESOLUTION

P: PRINTER/FILE I: I/O PORT

C : COLOR R : CHANGE GRID RATIO

V : VIEW SETTINGSL : SET PLOT CONTOURSU : UNITSQ : QUIT

W: WIND HEIGHT

- If you enter a selection, the HOTSPOT program will adjust the setting or prompt you for more information.
- Note: Select V to view settings when you want to know current settings (or after you have changed settings).

Codes A-T

: Plutonium Explosion **B**: Plutonium Fire **C**: Plutonium Resuspension : Uranium Explosion E: Uranium Fire : Nuclear Explosion : Radiation Workplace **H**: General Plume : General Explosion : General Resuspension K : Inhalation Dose Т : Tritium Release : HOTSPOT Library : General Fire : FIDLER Calibration and LUNG Screening Q: QUIT

Enter Selection

1-#15

Notes:

Codes A-T

Codes A-T

- The HOTSPOT Main Menu includes Codes A-T.
- To use HOTSPOT, type in the appropriate letter to make your selection. The codes are as follows:

: Plutonium Explosion B: Plutonium Fire C: Plutonium Resuspension : Uranium Explosion E: Uranium Fire : Nuclear Explosion : Radiation Workplace **H**: General Plume : General Explosion : General Resuspension K: Inhalation Dose : Tritium Release : HOTSPOT Library M: FIDLER Calibration : General Fire and LUNG Screening Q: QUIT

Enter Selection

QUIT (Q Key)

: Plutonium Explosion **B**: Plutonium Fire C: Plutonium Resuspension : Uranium Explosion E: Uranium Fire **F**: Nuclear Explosion : Radiation Workplace : General Plume : General Explosion : General Resuspension K: Inhalation Dose : Tritium Release : HOTSPOT Library : General Fire : FIDLER Calibration and LUNG Screening Q: QUIT

Enter Selection

1-#16

Notes:

Explain the QUIT option and the Q Key.

QUIT (Q Key)

- The HOTSPOT Main Menu contains a Q: QUIT selection.
- To quit the program from the Main Menu, simply type Q
- Some other HOTSPOT screens include the Quit option; in such cases, type Q if you wish to return to the main menu or quit the program.

Lesson 2 Plutonium Explosion Code A

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 2 – Plutonium Explosion, Code A

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a plutonium

explosion involving released material, using the Plutonium

Explosion Code A Atmospheric Dispersion Model of the HOTSPOT

Health Physics program.

Enabling:

- When you complete this lesson, you should be able to do the following:
 - Describe the graphical output for a Plutonium Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Plutonium Explosion output (tabular and graphical)
 - Given mock data, generate Plutonium Explosion output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 2–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives



2-#1

Notes:


Lesson Objectives

- At the end of this lesson, students will be able to model a plutonium explosion involving released material, using the Plutonium Explosion Code A Atmospheric Dispersion Model of the HOTSPOT Health Physics Codes program.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Plutonium Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Plutonium Explosion output (tables and graphs)
 - Given mock data, generate Plutonium Explosion output (tables and graphs)

Graphical Output and Assumptions—Plutonium Explosion



2-#2

- Have students refer to Page 2-3, Plutonium Explosion: Graphical Output.
- Discuss the assumptions concerning the Plutonium Explosion incident.

Reference

Graphical Output and Assumptions—Plutonium Explosion

- Page 2-3 illustrates output for a Plutonium Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - Deposition velocity of the respirable fraction (AMAD = 1 micron) is 1 cm/sec.
 - Deposition velocity of the non-respirable fraction (AMAD = 40 micron) is 8 cm/sec. The non-respirable fraction equals 1-f, where f is the respirable fraction. The default value for f is 0.2 (20 % of the material involved in the explosion has an AMAD of 1 micron). The non-respirable fraction is used for deposition estimates only, and does not contribute to the inhalation dose values.
 - Default alpha specific activity of weapons-grade plutonium is 0.081 Curies/gram.
 - Inhalation class is Y.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - In Operation Roller Coaster, a series of explosive release mitigation studies was carried out at the Department of Energy's Nevada Test Site. One of the tests, named Double Tracks, involved the explosive release of plutonium using 113 pounds of high explosive. The test was performed at three in the morning and the wind speed was 5 meters/second at a height of 2 meters. Compare the HOTSPOT estimates with the actual test measurements. The experimental results were normalized to a 1 kilogram initial mass of plutonium, so use 1 kg as the total mass of plutonium involved in the explosion (Dewart et al, 1982). The HOTSPOT output is in good agreement with the measured air concentration and ground deposition data.

Code Description: Plutonium Explosion

| HOTSPOT 7.0 | | PLUTON | IIUM EXPL | OSION | | | III | |
|------------------------|--------------------------|-----------------------------|-----------|-----------------------|--------------------------------|---|-------------------------|--|
| RADIONUCLIDE: | | PU-239 Inhalation Class : Y | | | | | | |
| HALFLIFE | 2.4E+04 yrs | | | | | | | |
| SOURCE TERM: | | 1.0E+00 kg | | | | | | |
| | RELEASE FRACTION: | | | 2.0E-01 | | | | |
| HIGH EXPLOSIVE | | 113.0 lbs | | | | | | |
| CLOUD TOP | | 248 m | • | | | | | |
| WIND SPEED (h = | = 2 m) | 5.0 m/s | | | | | | |
| STABILITY CLAS | • | D | | D | DEPOSITION VELOCITY: 1.00 cm/s | | 1.00 cm/s | |
| RECEPTOR HEIG | | 0.0 m | | | INVERSION LAYER HEIGHT: | | | |
| MAXIMUM DOSE | | <0.10 km | 1 | | AXIMUM C | | >8.4 rem | |
| Plume Centerline | 5101711102. | 40.10 tan | • | | , o timo timo | ,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,, | 70.110111 | |
| | | | | | | | | |
| D = 0.10 kr | n | D = | 0.20 km | | D = | 0.50 km | 1 | |
| DEP = 2.4E+0 |)1 mCi/m ² | DEP = | 1.9E+01 | mCi/m ² | DEP | = 1.2E+0 | 1 mCi/m ² | |
| CHI = 7.7E-0 | 95 (Ci-s)/m ³ | CHI = | 6.3E-05 | (Ci-s)/m ³ | CHI : | = 4.1E-05 | 5 (Ci-s)/m ³ | |
| | , , | | | | | | · , | |
| 50-YR DOSE CO | MMITMENT: | 50-YR D | OSE COM | MITMENT: | 50-Y | R DOSE COM | MITMENT: | |
| LUNG | 3.1E+01 rem | LUNG | | 2.5E+01 re | m LUN | G | 1.6E+01 rem | |
| SURFACE BONE | 9.0E+01 rem | SURFAC | E BONE | 7.3E+01 re | m SUR | FACE BONE | 4.8E+01 rem | |
| RED MARROW | 7.2E+00 rem | RED MA | RROW | 5.8E+00 re | m RED | MARROW | 3.8E+00 rem | |
| LIVER | 2.0E+01 rem | LIVER | | 1.6E+01 re | m LIVE | R | 1.1E+01 rem | |
| EFFECTIVE DOSE | | EFFECTIVE DOSE | | | EFF | EFFECTIVE DOSE | | |
| EQUIVALENT | 8.4E+00 rem | EQUIVA | LENT | 6.9E+00rer | m EQU | IVALENT | 4.5E+00 rem | |
| | | _ | | | _ | | | |
| D = 1.00 kr | | D= | 2.00 km | 211 2 | D= | 5.00 km | - | |
| | 00 mCi/m ² | DEP = | 4.8E+00 | | DEP | _ | 0 mCi/m ² | |
| CHI = 2.7E-0 | 95 (Ci-s)/m ³ | CHI = | 1.7E-05 | (Ci-s)/m ³ | CHI : | = 8.0E-06 | 6 (Ci-s)/m ³ | |
| 50-YR DOSE COM | MMITMENT: | 50-YR D | OSE COM | NITMENT: | 50-Y | R DOSE COM | MITMENT: | |
| LUNG | 1.1E+01 rem | LUNG | | 6.7E+00 re | | | 3.2E+00 rem | |
| SURFACE BONE | | | E BONE | 1.9E+01 re | _ | FACE BONE | 9.3E+00 rem | |
| RED MARROW | 2.5E+00 rem | | | 1.6E+00 re | | MARROW | 7.5E-01 rem | |
| LIVER | 7.0E+00 rem | | | 4.3E+00 re | | _ | 2.1E+00 rem | |
| EFFECTIVE DOS | | | IVE DOSE | | | ECTIVE DOSE | | |
| EQUIVALENT | 3.0E–00 rem | EQUIVAI | | 1.8E+00 re | | IVALENT | 8.8E-01 rem | |
| | | | | | | | | |
| D = 10.00 F | ĸm | D = | 20.00 km | | D= | 50.00 ki | m | |
| | 00 mCi/m ² | DEP = | 3.7E-01 | | DEP | _ | 2 mCi/m ² | |
| CHI = 4.2E-0 | 06 (Ci-s)/m ³ | CHI = | 2.0E-06 | (Ci-s)/m ³ | CHI : | = 6.9E-07 | 7 (Ci-s)/m ³ | |
| 50 VD DOOE 60 | ARAITRACNIT | 50 VD 5 | 005 001 | AITBAEL'T | 50.14 | D DOOF 00: | RAITRACLIT. | |
| 50-YR DOSE COMMITMENT: | | | OSE COM | - | | R DOSE COM | - | |
| LUNG | 1.7E+00 rem | LUNG | E DONE | 8.0E-01 re | | | 2.7E-01 rem | |
| SURFACE BONE | | | E BONE | 2.3E+00 re | | FACE BONE | 8.0E-01 rem | |
| RED MARROW | 3.9E–01 rem | RED MA LIVER | KKUW | 1.9E-01 re | | MARROW | 6.4E–02 rem | |
| | LIVER 1.1E+00 rem | | "/F DOCE | 5.2E-01 re | | | 1.8E-01 rem | |
| EFFECTIVE DOSE | | | IVE DOSE | 2.25 04 | | ECTIVE DOSE | | |
| EQUIVALENT | 4.6E–01 rem | EQUIVAI | LENI | 2.2E-01 re | ווו בעט | IVALENT | 7.5E–02 rem | |

2-#3

Notes:

 Describe the code used to derive the Plutonium Explosion Atmospheric Dispersion Model discussed in this lesson.

Code Description: Plutonium Explosion

Code description — Study the table on page 2-5.

HOTSPOT Health Physics Codes
VERSION 7.0
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

: Plutonium Explosion **C**: Plutonium Resuspension **B**: Plutonium Fire : Uranium Explosion E: Uranium Fire F: Nuclear Explosion : Radiation Workplace **H**: General Plume I : General Explosion : General T: Tritium Release **K**: Inhalation Dose Resuspension : HOTSPOT Library M: FIDLER Calibration N: General Fire and LUNG Screening Q: QUIT

Enter Selection

2-#4

- Describe the steps involved in using HOTSPOT to model Explosion incident involving Plutonium.
- Explain that the students should use the reference for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code A (Plutonium Explosion) from the HOTSPOT Main Menu.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- MASS (Pu), kg—Define mass as the total quantity of plutonium involved in the explosion (kilograms).
- ALPHA SPECIFIC ACTIVITY = 0.081 Ci/g ? (Y/N)—This is the default weapons-grade value; explain alpha specific activity to the students.


- Select Plutonium Explosion from the HOTSPOT Main Menu.
- Step 1 Type A
- MASS (Pu), kg

Enter the total quantity of plutonium involved in the explosion (kilograms), and push Enter.

- Step 2 Type 1; press Enter
- ALPHA SPECIFIC ACTIVITY = 0.081 Ci/g ? (Y/N)

Enter "Y" to accept the default weapons-grade value, or "N" if you wish to enter a new value.

• Step 3 Type Y; press Enter



2-#5

- HIGH EXPLOSIVE, LB?—Tell the students that this field requires the quantity of explosive (pounds). In this example, it is 113.
- F = 2.000E-01? (Y/N)—Explain the concept of "fraction of the entered activity."

HIGH EXPLOSIVE, LB?

Enter the quantity of explosive (pounds), and push Enter. Input must be greater than or equal to 0.1.

- Step 4 Type 113; press Enter
- F = 2.000E-01 ? (Y?N)

F is the fraction of entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

• Step 5 Type Y; press Enter

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A : A stability Very unstable

B : B stability Moderately unstable C : C stability Slightly unstable

D: D stability Neutral

E : E stability Slightly stable
F : F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

2-#6

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 3 indicates the correct meteorological condition (NIGHT).

• Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 6** Type **3** to indicate the meteorological condition (NIGHT).

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | <1 | <0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 – 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 - 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 - 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 - 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 - 75 | 28 – 34 |
| hurricane | | >75 | >34 |

2-#7

Notes:

• Wind—Refer students to the Wind screen display.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 7** Type **5**

Press the **Enter** key.

Main Output Options Menu

| Ма | Main Output Options Menu | | | | | | | | |
|--------|--------------------------|--------------------------------|--------------|-----------|-----------|--|--|--|--|
| 1 | : | SCREEN | Output | Default | Distances | | | | |
| 2 | : | SCREEN | Output | You Enter | Distances | | | | |
| 3 | : | PRINTER | Output | Default | Distances | | | | |
| 4 | : | PRINTER | Output | You Enter | Distances | | | | |
| 5 | : | DISK FILE | Output | Default | Distances | | | | |
| 6 | : | DISK FILE | Output | You Enter | Distances | | | | |
| G C | : | GRAPHICS Change DEFAULT CON | TOUR SETTING | SS | | | | | |

M : Change METEOROLOGICAL PARAMETERS and Release Height

Z : Change RECEPTOR HEIGHT (z)

D : Change DEPOSITION VELOCITY
 O : Enable prompt for OFF AXIS Positions
 I : INVERSION HEIGHT (Mixing Layer)
 Q : Enter to Main HOTSPOT Menu.

2-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 8 Type 1 to view data tables.

Press Enter view more data.

Continue pressing Enter until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

Output Option Number Menu

1: Enter a new Downwind Distance

2: Return to Output Menu

Q: Return to Main HOTSPOT Menu

2-#9

Notes:

• Explain that students must type **2** at the Output Option Number Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- **Step 9** Type **2** at the Output Option Number Menu to return to the Output Menu.

Press Enter

Enter to Main HOTSPOT Menu.

Main Output Options Menu—Option G

| Mai | Main Output Options Menu | | | | | | | | | |
|-----|--------------------------|---------------------------------|---------------|--------------------|-----------|--|--|--|--|--|
| 1 | : | SCREEN | Output | Default | Distances | | | | | |
| 2 | : | SCREEN | Output | You Enter | Distances | | | | | |
| 3 | : | PRINTER | Output | Default | Distances | | | | | |
| 4 | : | PRINTER | Output | You Enter | Distances | | | | | |
| 5 | : | DISK FILE | Output | Default | Distances | | | | | |
| 6 | : | DISK FILE | Output | You Enter | Distances | | | | | |
| | | | | | | | | | | |
| G | : | GRAPHICS | | | | | | | | |
| С | : | Change DEFAULT CON | TOUR SETTING | iS | | | | | | |
| М | : | Change METEOROLOG | ICAL PARAMET | ERS and Release He | eight | | | | | |
| Z | : | Change RECEPTOR HEIGHT (z) | | | | | | | | |
| D | : | Change DEPOSITION VELOCITY | | | | | | | | |
| 0 | : | Enable prompt for OFF A | XIS Positions | | | | | | | |
| ı | : | INVERSION HEIGHT (Mixing Layer) | | | | | | | | |

2-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident.

- Option G—Graphics
- **Step 10** Type **G** for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

2-#11

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color/Monochrome—Have students type the number 1 or 2.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same graph as Page 2-3).

- **Step 11** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

- **Step 12** Type **2** for monochrome, unless you have a color monitor, in which case, you must type 1
- Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


• **Step 13** Type **1**

The result is a graph.

- Print (if you have printer capability).
 - **Step 14** Press **P** to print the graph.

Exercise 2-1: Plutonium Explosion

• Exercise (Pu-239)



2-#12

- Distribute Exercise for Plutonium Explosion involving pu-239 (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = <0.1 km Maximum CEDE = >79 rem

Reference


Exercise 2-1: Plutonium Explosion

- Page 2-23 illustrates the graphical output for a Plutonium Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - Three kilograms of weapons-grade plutonium are involved in a one-point detonation (150 pounds of high explosive). The sun is low, and the wind speed is 1.5 meters per second. Estimate the ground contamination and dose commitments for locations downwind (centerline of plume) from the event. Assume default release fraction (20%) and specific activity (0.081 Ci/g).
- Step 1 From the HOTSPOT Main Menu, select A
- Step 2 MASS? Type 3; press Enter
- Step 3 Alpha Specific Activity? Type Y; press Enter
- Step 4 High Explosive? Type 150; press Enter
- **Step 5** F=? Type **Y** to accept the default value.
- **Step 6** Condition? Type **2** (for sun LOW in sky).
- Step 7 Wind? Type 1.5 (for 1.5 meters/second); press Enter
- **Step 8** Type **1** at the Main Outputs Options Menu to view data table; press **Enter** as desired to view more data.
- **Step 9** Type **1** at the Outputs Option Number Menu to enter downwind distance.
- **Step 10** Type **2** to return to the Output Menu.
- Step 11 Type G (graphics).
- **Step 12** Type **3** to view Centerline 50-yr. CEDE vs. Distance.
- Step 13 Type 1 to select color.
- **Step 14** Type **1** to enter downwind plotting range.

The result is the graph shown on the previous page of this manual.

Lesson 3 Plutonium Fire Code B

Lesson Objectives



3-#1


- At the end of this lesson, students should be able to model a plutonium fire involving released material, using the Plutonium Fire Code B Atmospheric Dispersion Model.
- Explain the Lesson Objectives.

Reference

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Plutonium Fire Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Plutonium Fire output (tables and graphs)
 - Given mock data, generate Plutonium Fire output (tables and graphs)

Graphical Output and Assumptions—Plutonium Fire



3-#2

- Have students refer to Page 3-3, Plutonium Fire: Graphical Output.
- Discuss the assumptions concerning the Plutonium Fire incident, as described on the Reference page.

Reference

Graphical Output and Assumption—Plutonium Fire

- Page 3-3 illustrates output for a Plutonium Fire Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - The default respirable fraction of the total plutonium involved in the fire that is released is 5x10⁻⁴ (0.05 %). The respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD), of 1 micrometer (See User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1 m AMAD particle size distribution.
 - The effective release height is determined using the methodology contained in the "Fuel Fire" section of Appendix A. Once the effective release height is determined, the radius of the final bent-over plume is set equal to 60% of the effective release height (Hanna, 1982). An upwind virtual point source, which results in an initial y and z equal to 50% of the plume radius at the origin (i.e., plume radius = 2), is used to model the fire scenario.
 - Deposition velocity is 1 cm/sec.
 - Default alpha specific activity of weapons-grade plutonium is 0.081 Curies/gram.
 - Inhalation class is Y.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - Three kilograms of weapons-grade plutonium are involved in a fire due to 30 gallons of fuel burning for fourteen minutes. The effective diameter of the fire zone is 20 meters. Use the default release fraction of 0.05% and assume the material was released during a 10-minute time period (10 minutes is the default HOTSPOT value) during the 14-minute fire duration. The sun has set, the wind speed is 2 meters/second, and the temperature is 20 degrees centigrade. Estimate the 50-year committed effective dose commitments to individuals remaining downwind throughout the entire fire.

Code Description: Plutonium Fire

| HOTSPOT 7.0 | PLUTONIUM FIRE | |
|---|--|------------------------------|
| HOTSPOT 7.0 RADIONUCLIDE: HALFLIFE: SOURCE TERM RELEASE FRACTION: | PU-239 Inhalation Class: Y | |
| HALFLIFE : | 2.4E+04 Years | |
| SOURCE TERM : | 3.0E+00 kg | |
| RELEASE FRACTION: | 5.0E-04 | |
| FUEL : | 3.0E+01 gal FIRE DURATION | : 14.00 min |
| EFFECTIVE RELEASE HEIGHT : | 40.00 m | |
| WIND SPEED $(h = 2 m)$ | 40.00 m 2.0 m/s RELEASE RADIUS | : 10 m |
| FUEL FUEL EFFECTIVE RELEASE HEIGHT: WIND SPEED (h = 2 m): WIND SPEED (h = H-eff): STABILITY CLASS: RECEPTOR HEIGHT: SAMPLE TIME: | 5.7 m/s | |
| STABILITY CLASS | F DEPOSITION VELO | OCITY : 1.00 cm/s |
| RECEPTOR HEIGHT | 0.0 m INVERSION LAYER | R HEIGHT : NONE |
| SAMPLE TIME | 10.0 min | CHEIGHT .HONE |
| MAXIMUM DOSE DISTANCE | 0.67 km MAXIMUM CEDE | · 0.160 rem |
| Plume Centerline | 0.07 Km | . 0.100 10111 |
| Traine Centenine | | |
| D = 0.10 km | D = 0.20 km DEP = 7.3E-03 uCi/m^2 CHI = 7.3E-07 (Ci-s)/m^3 | D = 0.50 km |
| DEP = 3.7E-03.uCi/m/2 | DEP = 7.3E-03 uCi/m^2 | DEP = 1.4E-02 µCi/m^2 |
| CHI = 3.7E-07 (Ci-s)/m/3 | CHI = 7.3E-03 dOM1 2 | CHI = 1.4E-06 (Ci-s)/m/3 |
| 0111 = 3.7 E-07 (OI-3)/111 3 | OH = 7.3E-07 (OF-9)/HF-3 | CITI = 1:4E-00 (CI-3)/III 3 |
| 50-YR DOSE COMMITMENT: | 50-YR DOSE COMMITMENT: | 50-YR DOSE COMMITMENT: |
| | | |
| LUNG 1.5E-01 rem | LUNG 2.9E-01 rem SURFACE BONE 8.5E-01 rem RED MARROW 6.8E-02 rem | LUNG 5.6E-01 rem |
| SURFACE BONE 4.3E-01 rem | SURFACE BONE 8.5E-01 rem | SURFACE BONE 1.6E+00 rem |
| RED MARROW 3.4F-02 rem | RED MARROW 6.8F-02 rem | RED MARROW 1.3E-01 rem |
| LIVER 9.6F-02 rem | LIVER 1 9F-01 rem | LIVER 3.6E-01 rem |
| EFFECTIVE DOSE | EFFECTIVE DOSE | EFFECTIVE DOSE |
| FOUIVALENT 4 1F-02 rem | LIVER 1.9E-01 rem EFFECTIVE DOSE EQUIVALENT 8.0E-02 rem | EQUIVALENT 1.5E-01 rem |
| 4.1E 02 16111 | EQUIVALENT 0.0E 02 ICIII | EQUIVALENT 1.5E OTTOM |
| | | |
| D = 1.00 km | D = 2.00 km DEP = 7.9E-03 uCi/m^2 CHI = 7.9E-07 (Ci-s)/m^3 | D = 5.00 km |
| DEP = 1.3E-02 µCi/m^2 | DEP = 7.9E-03.uCi/m^2 | DEP = 2.7E-03.uCi/m^2 |
| CHI = 1.3E-06 (Ci-s)/m^3 | CHI = 7.9E-07 (Ci-s)/m/3 | CHI = 2.7E-07 (Ci-s)/m^3 |
| 0111 = 1.52 00 (013)/111 5 | 0111 = 1.5E 01 (013)/111 3 | 0111 = 2.7 E 07 (01 3)/111 0 |
| 50-YR DOSE COMMITMENT: | 50-YR DOSE COMMITMENT: | 50-YR DOSE COMMITMENT: |
| | | |
| LUNG 5.3E-01 rem | LUNG 3.1E-01 rem | LUNG 1.1E-01 rem |
| LUNG 5.3E-01 rem SURFACE BONE 1.6E+00 rem RED MARROW 1.2E-01 rem | SURFACE BONE 9.2E-01 rem | |
| RED MARROW 1.2F-01 rem | SURFACE BONE 9.2E-01 rem RED MARROW 7.3E-02 rem | RED MARROW 2.5E-02 rem |
| LIVER 3.5F-01 rem | LIVER 2.0F-01 rem | LIVER 6.9E-02 rem |
| EFFECTIVE DOSE | EFFECTIVE DOSE | EFFECTIVE DOSE |
| EOUIVALENT 1.5E-01 rem | LIVER 2.0E-01 rem EFFECTIVE DOSE EQUIVALENT 8.6E-02 rem | EQUIVALENT 2.9E-02 rem |
| LQUIVALLINI I.JL-UI IGIII | EQUIVALENT 0.0E-02 (CIII | LOCULARION 2.3L-02 IGIII |
| | | |

3#3

Notes:

 Describe the code used to derive the Plutonium Fire Atmospheric Dispersion Model illustrated in this lesson.

Code Description: Plutonium Fire

• Code description — Study the table on page 3-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|---------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | I: General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: General Fire |
| | | | | Q: QUIT |

Enter Selection

3-#4

- Describe the steps involved in using HOTSPOT to model the plutonium fire incident.
- Explain that the student can use the Reference page for detailed information.
- Code—Explain that the students must select the specific code related to the ttype of incident. In this example, they must select Code B (Plutonium Fire) from the HOTSPOT Main Menu.
- Effective Release Height—Explain the conditions under which the students would select 1, 2, or 3 from the Effective Release Height menu.
- MASS (PU), kg—Explain that the students must enter the total quanity (in kilograms) of plutonium involved in the fire.


Reference

Demonstration: Plutonium Fire

- Select Plutonium Fire from the HOTSPOT Main Menu.
- Step 1 Type B
- Result The Effective Release Height menu appears:
 - 1: Fire –You enter Effective Release Height.
 - 2: Fire HOTSPOT calculates Effective Release Height using input fuel and burn duration.
 - Fire HOTSPOT calculates Effective Release Height using input Heat Emission (calories per second).
- **Step 2** Type **2**
- MASS (Pu), kg

Enter the total quantity of plutonium involved in the explosion (kilograms), and push Enter.

• Step 3 Type 3; press Enter



3-#5

- ALPHA SPECIFIC ACTIVITY= 0.081 Ci/g?—This is the default weapons-grade value; explain alpha specific activity to the students.
- Volume of FUEL (gallons)—This is the total amount of fuel burned in the fire; in this example, it is 30 gallons.
- Release Radius = 10 m? (Y/N)—Describe the effective radius of the fire; for example, radius of the fuel pool.

• ALPHA SPECIFIC ACTIVITY = 0.081 Ci/g ? (Y/N)

Enter "Y" to accept the default weapons-grade value, or "N" if you wish to enter a new value.


- Step 4 Type Y
- Volume of FUEL (gallons)?

Enter the total amount of fuel burned in the fire, and push Enter. Note: assumed heat of combustion is 12,000 calories/gram.

- Step 5 Type 30; press Enter
- Release Radius = 10 (m)?

Release radius is the effective radius of the fire, e. g., radius of burning fuel pool. The default is 10 meters.

• Step 6 Type Y



3-#6

- Burn Time (minutes)—Explain burn time; in this example, it is 20 minutes.
- Ambient Air Temperature = 20 degrees C? (Y/N)—Define the ambient air temperature.
- F= 5.000E-04? (Y/N)—Explain the concept of "fraction of the entered activity."

• Burn Time (minutes)?

Enter the burn time duration of the fire, and push Enter.

- Step 7 Type 20; press Enter
- Ambient Air Temperature = 20 degrees C? (Y/N)

The default value for the ambient temperature is 20 degrees centigrade (293 kelvin).

Note: centigrade = (Fahrenheit-32) / 1.8

- Step 8 Type Y
- $F = 5.000E^{-04}? (Y/N)$

The default respirable fraction of the plutonium involved in the fire that is released is 5×1^{-4} (0.05%).

Step 9 Type Y

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

3#7

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition or enter a letter (A-G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 3 indicates the correct meteorological condition (NIGHT).

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 10** Type **3** to indicate meteorological condition (NIGHT).

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 - 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 - 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 - 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 - 75 | 28 – 34 |
| hurricane | - | > 75 | > 34 |

3-#8

Notes

• Wind—Refer students to the Wind screen display.

WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 11** Type **2**

Press the Enter key.

Plume Rise Summary Information

The Plume Rise Summary Information table allows you to verify that you have entered the correct information in each of the fields.

Plume Rise Summary Information

Fuel Burned : 30.00 gallons Burn Duration : 14 minutes

Heat Emission : 9.2 E+05 calories/second
Buouancy Flux : 3.4E+01 meters^4/second^3
Ambient Air Temperature : 20.0 degrees centigrade

Released Radius : 10.0 meters
Average Windspeed : 5.7 meters/sec
Effective Release Height : 40 meters

• Step 12 Press Enter

Main Output Options Menu

Main Output Options Menu

- 1: SCREEN Output Default **Distances** 2: SCREEN Output You Enter **Distances** Default 3: PRINTER Output **Distances** 4: PRINTER Output You Enter Distances 5: DISK FILE Output Default Distances 6: DISK FILE Output You Enter **Distances**
- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- P: Plume Rise
- T: Sample Time
- R: Review Plume Rise Data
- Q: Enter to Main HOTSPOT Menu.

3-#9

- Screen ouput—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

Reference

Demonstration: Plutonium Fire

- Main Outputs Options Menu
- Screen output
- Step 13 Type 1 to view data tables.

Press **Enter** to view more data.

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- Output Option Number Menu
- 1: Enter a new Downwind Distance.
- 2: Return to Output Menu.
- Q: Return to Main HOTSPOT Menu.

3-#10

Notes:

• Explain that students must type 2 at the Output Option Number Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- Step 14 Type 2 at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- P: Plume Rise
- T: Sample Time
- R: Review Plume Rise Data
- Q: Enter to Main HOTSPOT Menu.

3-#11

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident.

- Option G—Graphics
- **Step 15** Type **G** for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

3-#12

- Output Option Number Menu—Explain this menu.
- Students may view Centerline 50-yr CEDE vs. Distance graphical output by typing the number 3.
- Color/Monochrome—Have students type 1 for color.
- Downwind Plotting Range—Have students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same results as on Page 3-3).

- **Step 16** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

- Step 17 Type 1 for color monitor.
- Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


• **Step 18** Type **1**

The result is a graph.

- Print (if you have printer capability).
- **Step 19** Press **P** to print the graph.

Exercise 3-1: Plutonium Fire

• Exercise (Pu-239)



3#13

- Distrubute Exercise for Plutonium Fire involving PU-239.
- Display Overhead.
- Explaign that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = 2.0 km, Maximum CEDE = 0.045 rem

Reference

Exercise 3-1: Plutonium Fire

- Page 3-25 illustrates the graphical output for a Plutonium Fire Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - Seven kilograms of weapons-grade plutonium are involved in a fire due to 100 gallons of fuel burning for twenty minutes. The effective radius of the fire zone is 3 meters. Use the default release fraction of 0.05%. It is nighttime, the wind speed is 2 meters/second, and the temperature is 10 degrees centigrade. Estimate the 50-year committed effective dose commitments to individuals remaining downwind throughout the entire fire.

| • | Step 1 | From the HOTSPOT Main Menu, | select B | | |
|---|---------|---|---|--|--|
| • | Step 2 | Output Option | Type 2 | | |
| • | Step 3 | MASS? | Type 7; press Enter | | |
| • | Step 4 | Alpha Specific Activity? | Type Y | | |
| • | Step 5 | Volume of FUEL? | Type 100 ; press Enter | | |
| • | Step 6 | Release Radius = 3.47 m? (Y/N) | Type N ; type 3 ; press Enter | | |
| • | Step 7 | Burn Time? | Type 10; press Enter | | |
| • | Step 8 | Ambient Air Temp. = 20°C? | Type N ; type 10 ; press Enter | | |
| • | Step 9 | $F = 5.000E^{-04}? (Y/N)$ | Type Y | | |
| • | Step 10 | Conditions? | Type 3 for NIGHT. | | |
| • | Step 11 | Wind? | Type 2 (for 2 | | |
| | | | meters/second); press Enter | | |
| • | Step 12 | Plume Rise Summary Information | n appears; press Enter | | |
| • | Step 13 | Type 1 at the Main Outputs Options Menu to view data table; press Enter as desired to view more data. | | | |
| • | Step 14 | Type 1 at the Outputs Option Number Menu to enter downwind distance. | | | |
| • | Step 15 | Type 2 to return to the Output Menu. | | | |
| • | Step 16 | Type G (graphics). | | | |
| • | Step 17 | Type 3 to view Centerline 50-yr. | CEDE vs. Distance. | | |
| • | Step 18 | Type 1 to select COLOR. | | | |
| • | Step 19 | Type 1 to enter downwind plotting | g range. | | |

The result is the graph shown on the previous page of this manual.

Lesson 4 Plutonium Resuspension Code C

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 4 – Plutonium Resuspension, Code C

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a plutonium

resuspension involving released material, using the Plutonium

Resuspension Code C Atmospheric Dispersion Model

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Plutonium Resuspension Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Plutonium Resuspension output (tabular and graphical)
 - Given mock data, generate Plutonium Resuspension output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 4–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




4-#1

- At the end of this lesson, students will be able to model a plutonium resuspension involving released material, using the Plutonium Resuspension Code C Atmospheric Dispersion Model.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to do the following:
 - Identify the graphical output for a Plutonium Resuspension Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Plutonium Resuspension output (tables and graphs)
 - Given mock data, generate Plutonium Resuspension output (tables and graphs)

Graphical Output for Plutonium Resuspension



4-#2

- Have the students refer to Page 4-3, Plutonium Resuspension: Graphical Output.
- Discuss the assumptions involved in this incident, as described on the Reference page.

Reference

Graphical Output and Assumptions—Plutonium Resuspension

- Page 4-3 illustrates output for a Plutonium Resuspension Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program
- This example is based on the following assumptions:
 - Resuspension is modeled using the methodology contained in the "Resuspension" section of Appendix A (User Manual).
 - Inhalation class is Y.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - There has been a plutonium contamination event. Estimate the 50-year committed effective dose equivalent rates (i.e., dose commitment per hour of downwind exposure) to individuals downwind from a two-week-old plutonium contamination event. Most of the plutonium is contained in an area with an effective radius of 100 meters. The average contamination level is 150 microcuries/square meter. Assume nighttime conditions with a wind speed of 1 meter/second.

Code Description: Plutonium Resuspension

| нотѕро | T 7 0 | | PI LITONI | IIM RESI | ISPENSION | | | | |
|-------------------------------|------------------------|--------------------------|--|-------------------|------------------------|----------------|-------------|-------------------|-------------|
| | | | PLUTONIUM RESUSPENSION PU-239 Inhalation Class : Y | | | | | | |
| | | | 2.4E+04 yrs | | | | | | |
| | | 5.7E-05 1 | | | | | | | |
| EFF. RAD | | 01011. | 100 m | , | | | | | |
| | POSITION | | 1.5E+02u | Ci/m ² | | | | | |
| | INATION A | GF· | 1.5E+626 14 days | Ci/III | | | | | |
| | VE RELEAS | * | 0.00 m | | | | | | |
| | PEED (h = 2 i | _ | 1.0 m/s | | | DEPOSIT | ION VELOCIT | TY· | 1.00 cm/s |
| | Y CLASS: | , | F.011//3 | | | | ON LAYER HE | | |
| _ | OR HEIGHT | | 0.0 m | | | MAXIMUN | | | >0.651 rem |
| SAMPLE | _ | | 60.0 min | | | | 0252. | | 20.00110111 |
| | M DOSE DIS | STANCE: | < 0.10 km | | | | | | |
| Plume Ce | | JITHOL. | < 0.10 KIII | | | | | | |
| 1 101110 00 | | | | | | | | | |
| D= | 0.10 km | | D = | 0.20 km | | D = | 0.50 km | | |
| CHI = | 1.6E-09 C | Ci/m ³ | CHI = | 1.0E-09 | Ci/m ³ | CHI = | 4.8E-10 | Ci/m ³ | |
| | | | | | | | | | |
| | OSE COMMI | - | 50-YR DOSE COMMITMENT: | | 50-YR DOSE COMMITMENT: | | | | |
| LUNG | | 2.4E+00 rem | LUNG | | 1.5E+00rem | | | | 01 rem |
| SURFACE BONE 6.9E+00rem | | SURFACE BONE 4.4E+00 rem | | | ACE BONE | | 00 rem | | |
| | ARROW 5.5E+01 rem | | RED MAR | RROW | 3.5E-01 rem | | IARROW | | 01 rem |
| | LIVER 1.5E+00rem | | LIVER | | 9.8E-01 rem | | | 4.5E- | 01 rem |
| | VE DOSE | | EFFECTI | | | | CTIVE DOSE | | |
| EQUIVAL | ENT. | 6.5E-01 rem | EQUIVAL | ENT | 4.1E-01 rem | EQUIV | ALENT | 1.9E-0 | 01 rem |
| D= | 1.00 km | | D= | 2.00 km | | D= | 5.00 km | | |
| CHI = | 2.2E-10 C | :/m 3 | CHI = | 7.7E-11 | Ci/m3 | CHI = | 1.3E-11 | | |
| Cni = | 2.2E-10 C | 1/111 - | CHI = | 7.76-11 | CI/III · | CHI = | 1.3E-11 | Ci/iii | |
| 50-YR D | OSE COMMI | TMENT: | 50-YR DOSE COMMITMENT: | | 50-YR | DOSE COM | MITMEN | IT: | |
| LUNG | | 3.2E+01 rem | LUNG | | 1.1E-01 rem | LUNG | | 1.9E-0 | 02 rem |
| SURFAC | E BONE | 9.2E-01 rem | SURFAC | E BONE | 3.2E-01 rem | SURF | ACE BONE | 5.6E-0 | 02 rem |
| RED MAI | RED MARROW 7.4E-02 rem | | RED MARROW 2.6E-02 rem | | RED MARROW 4.5E | | 4.5E-0 | 03 rem | |
| LIVER | | 2.1E-01 rem | LIVER | | 7.2E-02 rem | LIVER 1.3E | | 1.3E-0 | 02 rem |
| EFFECTI | EFFECTIVE DOSE | | EFFECTI | VE DOSE | | EFFECTIVE DOSE | | | |
| EQUIVALENT 8.7E–02 rem | | EQUIVAL | ENT | 3.0E-02 rem | EQUIV | ALENT | 5.3E-0 | 03 rem | |
| | | | | | | | | | |
| | | | | | | | | | |
| | | | | | | | | | |

4-#3

Notes:

 Describe the code used to derive the Plutonium Resuspension Atmospheric Dispersion Model illustrated in this lesson.

Code Description: Plutonium Resuspension

• Code description — Study the table on page 4-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

A: Plutonium Explosion B: Plutonium Fire **C**: Plutonium Resuspension **D**: Uranium Explosion E: Uranium Fire F: Nuclear Explosion **G**: Radiation Workplace **H**: General Plume I : General Explosion : General **K**: Inhalation Dose T: Tritium Release Resuspension : HOTSPOT Library **M**: FIDLER Calibration N: General Fire and LUNG Screening Q: QUIT

Enter Selection

4-#4

- Describe the steps involved in using HOTSPOT to model the incident involving a Plutonium Resuspension event.
- Explain that the students should use the Reference page for detailed information.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code C (Plutonium Resuspension) from the HOTSPOT Main Menu.
- DEP, (μCi/square meter)—Define "average ground deposition" for the students.
- Release Radius? (m)—Explain that release radius is the effective radius of a circle containing 95% of the contamination (meters).

- Select Plutonium Resuspension from the HOTSPOT Main Menu.
- Step 1 Type C
- DEP, (μCi/square meters)

Enter the average ground deposition (microcuries/square meter), and push Enter.

- Step 2 Type 150
- Release Radius? (m)

Enter the effective radius of a circle containing 95% of the contamination.

• Step 3 Type 100; press Enter

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G G stability Special stability, low wind

Enter selection

4-#6

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 3 indicates the correct meteorological condition (NIGHT).

• Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 4** Type **3** to indicate meteorological conditions (NIGHT).

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 – 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 – 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 – 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

4#7

Notes:


• Wind—Refer students to the Wind screen display.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 5** Type **1**

Press the **Enter** key.



4-#5

- AGE, Days—Tell the students that AGE is the time since the contamination event; in this example, it is 14 days.
- S = 5.7E⁻⁰⁵? (Y/N)—Discuss with the students the resuspension factor for this 14-day-old contamination event. The default is Y, the correct choice in this example.

• Age, Day

Enter the time since the contamination event, (days), and push Enter.

- Step 6 Type 14; press Enter
- $S = 5.7E^{-0.5}? (Y/N)$

S is the resuspension factor (1/meter), for the 14-day-old contamination event. Enter "Y" to accept the above default value, or "N" if you wish to enter a new value.

• Step 7 Type Y

• Main Output Options Menu

| Main Output Options Menu | | | | | | | |
|--------------------------|---|--------|-----------|-----------|--|--|--|
| 1: | SCREEN | Output | Default | Distances | | | |
| 2: | SCREEN | Output | You Enter | Distances | | | |
| 3: | PRINTER | Output | Default | Distances | | | |
| 4: | PRINTER | Output | You Enter | Distances | | | |
| 5: | DISK FILE | Output | Default | Distances | | | |
| 6: | DISK FILE | Output | You Enter | Distances | | | |
| G: | GRAPHICS | | | | | | |
| C: | Change DEFAULT CONTOUR SETTINGS | | | | | | |
| M: | Change METEOROLOGICAL PARAMETERS and Release Height | | | | | | |
| Z: | Change RECEPTOR HEIGHT (z) | | | | | | |
| D: | Change DEPOSITION VELOCITY | | | | | | |
| O: | Enable prompt for OFF AXIS Positions | | | | | | |
| l: | INVERSION HEIGHT (Mixing Layer) | | | | | | |
| Т | SAMPLE TIME | | | | | | |
| Q: | Enter to Main HOTSPOT Menu. | | | | | | |

4-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Enter to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 8 Type 1 to view data tables.
- Step 9 Press Enter to view more data.

Continue pressing Enter until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- Output Option Number Menu
 - 1: Enter a new Downwind Distance.
 - 2: Return to Output Menu.
 - Q: Return to Main HOTSPOT Menu.

4-#9

Notes:

 Screen output—Explain that students should select 2 to return to the output menu.

- Output Option Number Menu
- **Step 10** Type **2** at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

| Main Output Options Menu | | | | | | | |
|--------------------------|---|--------|-----------|-----------|--|--|--|
| 1: | SCREEN | Output | Default | Distances | | | |
| 2: | SCREEN | Output | You Enter | Distances | | | |
| 3: | PRINTER | Output | Default | Distances | | | |
| 4: | PRINTER | Output | You Enter | Distances | | | |
| 5: | DISK FILE | Output | Default | Distances | | | |
| 6: | DISK FILE | Output | You Enter | Distances | | | |
| G: | GRAPHICS | | | | | | |
| C: | Change DEFAULT CONTOUR SETTINGS | | | | | | |
| M: | Change METEOROLOGICAL PARAMETERS and Release Height | | | | | | |
| Z: | Change RECEPTOR HEIGHT (z) | | | | | | |
| D: | Change DEPOSITION VELOCITY | | | | | | |
| O: | Enable prompt for OFF AXIS Positions | | | | | | |
| l: | INVERSION HEIGHT (Mixing Layer) | | | | | | |
| Т | SAMPLE TIME | | | | | | |
| Q: | Enter to Main HOTSPOT Menu. | | | | | | |

4-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident's air dispersion model.

- Option G—Graphics
- **Step 11** Type **G** for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: Centerline 50-yr. CEDE vs. Distance

TO PRINT GRAPHICS—PUSH the "P" key when thescreen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU

4-#11

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 2.
- Color/Monochrome—Have students type the number 1 or 2.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as Page 4-3).

• **Step 12** Type **2** to view Centerline 50-yr. CEDE vs. Distance graphical output.

Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

• **Step 13** Type **2** for monochrome, unless you have a color monitor, in which case, you must type 1

Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km

2: 0.1 TO 100 km


• **Step 14** Type **2**

The result is a graph.

- Print (if you have printer capability).
- **Step 15** Press **P** to print the graph.

Exercise 4-1: Plutonium Resuspension

Exercise (Pu-239)



4-#12

- Distribute Exercise for Plutonium Resuspension involving pu-239 (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = <0.1 km
 Maximum CEDE = >2.1 rem

Exercise 4-1: Plutonium Resuspension

- Page 4-23 illustrates the graphical output for a Plutonium Resuspension Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - There has been a plutonium contamination event. Estimate the 50-year committed effective dose equivalent rates (i.e., dose commitment per hour of downwind exposure) to individuals downwind from a one-day-old plutonium contamination event. Most of the plutonium is contained in an area with an effective radius of 150 meters. The average contamination level is 300 microcuries/square meter. Assume nighttime conditions with a wind speed of 1 meter/second.
- Step 1 From the HOTSPOT Main Menu, select C
- Step 2 Deposition? Type 300; press Enter
- Step 3 Release Radius? Type 150
- **Step 4** Conditions? Type **3** for NIGHT.
- Step 5 Wind? Type 1 (for 1 meter/second); press Enter
- Step 6 Age, Day? Type 1; press Enter
- **Step 7** $S = 8.6E^{-0.5}? (Y/N)$ Type **Y**
- Step 8 Type 1 at the Main Outputs Options Menu to view data table.
- **Step 9** Press **Enter** as desired to view more data.
- **Step 10** Type **2** to return to the Output Menu.
- **Step 11** Type **G** (graphics).
- **Step 12** Type **2** to view Centerline 50-yr. CEDE vs. Distance.
- Step 13 Type 1 to select COLOR.
- **Step 14** Type **1** to enter downwind plotting range.

The result is the graph shown on the previous page of this manual.

Lesson 5 Uranium Explosion Code D

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 5 – Uranium Explosion, Code D

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a uranium

explosion involving released material, using the Uranium Explosion Code D Atmospheric Dispersion Model of the HOTSPOT Health

Physics program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Uranium Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Uranium Explosion output (tabular and graphical)
 - Given mock data, generate Uranium Explosion output (tabular and graphical) using HOTSPOT

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 5–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




5-#1

- At the end of this lesson, students will be able to model a uranium explosion involving released material, using the Uranium Explosion Code D Atmospheric Dispersion Model.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Uranium Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Uranium Explosion output (tables and graphs)
 - Given mock data, generate Uranium Explosion output (tables and graphs)

Graphical Output and Assumptions—Uranium Explosion



5-#2

- Have students refer to Page 5-3, Uranium Explosion: Graphical Output.
- Discuss the assumptions concerning the Uranium Explosion incident.

Reference

Graphical Output and Assumptions—Uranium Explosion

- Page 5-3 illustrates output for a Uranium Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - The default respirable fraction of the total uranium involved in the explosion that is released is 0.20 (20 %). The respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD) of 1 micrometer (see User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1 m AMAD particle size distribution.
 - The release fraction is partitioned as described in Appendix A, "Explosive Release," (User Manual).
 - Deposition velocity of the respirable fraction (AMAD = 1 micron) is 1 cm/sec.
 - Deposition velocity of the non-respirable fraction (AMAD = 40 micron) is 8 cm/sec. The non-respirable fraction equals 1-f, where f is the respirable fraction. The default value for f is 0.2 (20 % of the material involved in the explosion has an AMAD of 1 micron). The non-respirable fraction is used for deposition estimates only, and does not contribute to the inhalation dose values.
 - Specific activity, S (Ci/g), as a function of U-235 enrichment, is (Alexander, 1974) S = $(0.4 + 0.38E + 0.0034E^2)(10^{-6})$, where E = percent enrichment. This equation includes the contribution from U-234.
 - Inhalation class is Y.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - Three kilograms of weapons-grade uranium (90% U-235, 10% U-238) are involved in a one-point detonation of a weapon containing 40 pounds of high explosive. The sun is low in the sky, and the wind speed is 1 meter/second. Estimate the ground contamination and 50-year committed effective dose equivalents as a function of down-wind centerline distance.

Code Description: Uranium Explosion

URANIUM EXPLOSION HOTSPOT 7.0 RADIONUCLIDE: URANIUM Inhalation Class: Y SPECIFIC ACTIVITY: 6.2E-05 Ci/g SOURCE TERM : 3.0E+00 kg RELEASE FRACTION: 2.0E-01 HIGH EXPLOSIVE : 40.0 lbs CLOUD TOP : 191 m WIND SPEED (h=2 m): 1.0 m/s STABILITY CLASS : B
RECEPTOR HEIGHT : 0.0 m DEPOSITION VELOCITY : 1.00 cm/s INVERSION LAYER HEIGHT: NONE MAXIMUM DOSE DISTANCE : < 0.1 km MAXIMUM CEDE : > 0.058 rem Plume Centerline D = 0.10 km D = 0.20 km D = 0.50 km3.3E-01 uCi/m^2 4.4E-01 uCi/m^2 DEP = DEP = $DEP = 1.7E-01 \text{ uCi/m}^2$ CHI = 1.4E-06 (Ci-s)/m^3 CHI = 1.1E-06 (Ci-s)/m^3 $CHI = 5.8E-07 (Ci-s)/m^3$ 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: LUNG LUNG EFFECTIVE DOSE **EFFECTIVE DOSE** EFFECTIVE DOSE 5.8E-02 rem 4.3E-02 rem 2.3E-02 rem EQUIVALENT EQUIVALENT EQUIVALENT 1.00 km 2.00 km 5.00 km DEP = 7.3E-02 uCi/m^2 DEP = 2.2E-02 uCi/m^2 DEP = 3.6E-03 uCi/m^2 CHI = 2.7E-07 (Ci-s)/m^3 CHI = 9.2E-08 (Ci-s)/m^3 CHI = 1.8E-08 (Ci-s)/m^3 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 1.1E-02 rem EQUIVALENT 3.7E-03 rem **EQUIVALENT** 7.4E-04 rem 10.00 km D = 20.00 km D = 50.00 km DEP = 8.8E-04 uCi/m^2 DEP = 2.2E-04 uCi/m^2 DEP = 3.8E-05 uCi/m^2 5.4E-09 (Ci-s)/m^3 1.6E-09 (Ci-s)/m^3 CHI = 3.5E-10 (Ci-s)/m^3 CHI = 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: LUNG LUNG EFFECTIVE DOSE **EFFECTIVE DOSE** EFFECTIVE DOSE 2.1E-04 rem 1.4E-05 rem EQUIVALENT EQUIVALENT 6.4E-05 rem **EQUIVALENT**

5-#3

Notes:

 Describe the code used to derive the Uranium Explosion Atmospheric Dispersion Model discussed in this lesson.

Code Description: Uranium Explosion

• Code description — Study the table on page 5-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: | Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|----|------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: | Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | I: | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: | Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: | General Fire |
| | | | | | Q: QUIT |

Enter Selection

5-#14

- Describe the steps in using HOTSPOT to model the explosion incident involving uranium.
- Explain that the students should use the Reference page for detailed information.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code D (Uranium Explosion) from the HOTSPOT Main Menu.
- Natural Uranium? (Y/N)—Describe natural uranium to the students. They
 need to type N to enter a new value (% U-235); in this example, they type
 90 after they type N.
- Specific Activity = 6.21E⁻⁰⁵ Ci/g ? (Y/N)—This is the default weapons-grade value; explain specific activity to the students.


- Select Uranium Explosion from the HOTSPOT Main Menu.
- Step 1 Type D
- Natural Uranium? (Y/N)

Enter percent U-235, and push Enter.

- Step 2 Type N; type 90; press Enter
- Specific Activity = 6.21E⁻⁰⁵ Ci/g (Y/N)?

Enter "Y" to accept the default weapons-grade value, or "N" if you wish to enter a new value.

Step 3 Type Y



5-#5

- MASS?—Define mass for the students. It is the total quantity of uranium involved in the explosion (kilograms).
- Fraction = 2.000E⁻⁰¹?—Define "fraction" and explain that the default respiration fraction of the total material involved in the explosion is dependent upon the type of material. Typing "Y" means that they accept the default.
- High Explosive, lb?—Tell the students to enter the quantity of explosive (pounds).

MASS, kg?

Enter the total quantity of uranium involved in the explosion (kilograms), and push Enter.

- Step 4 Type 3; press Enter
- $F = 2.000E^{-01}$?

F is the fraction of entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

- Step 5 Type Y
- High Explosive, lb?

Enter the quantity of explosive (pounds), and push Enter. Input must be greater than or equal to 0.I.

• **Step 6** Type **40**

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

5-#6

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 2 indicates the correct meteorological condition.

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 7** Type **2** to indicate meteorological condition (sun LOW in the sky).

Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 - 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 - 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 - 75 | 28 – 34 |
| hurricane | • | > 75 | > 34 |

5-#7

Notes:

• Wind—Refer students to the Wind screen display.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 8** Type **1**

Press the **Enter** key.

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Enter to Main HOTSPOT Menu.

5-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 9 Type 1 to view data tables.
- Step 10 Press Enter view more data

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- Output Option Number Menu
- 1: Enter a new Downwind Distance.
- 2: Return to Output Menu.
- Q: Return to Main HOTSPOT Menu.

5-#9

Notes:

• Tell students to type 2 at the Output Option Number Menu to return to the Output Menu.

- Output Option Number Menu
- **Step 11** Type **2** at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Enter to Main HOTSPOT Menu.

5-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident's air dispersion model.

- Option G—Graphics
- Step 12 Type G for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: Centerline 50-yr. CEDE vs. Distance

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

5-#11

- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color/Monochrome—Have students type the number 1 or 2.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as Page 5-3).

- **Step 13** Type **2** to view Centerline 50-yr. CEDE vs. Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

- **Step 14** Type **2** for monochrome, unless you have a color monitor, in which case, you must type 1.
- Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


• **Step 15** Type **1**

The result is a graph.

- Print (if you have printer capability).
- **Step 16** Press **P** to print the graph.

Exercise 5-1: Uranium Explosion

• Exercise (Uranium: U-235, U238)



5-#12

- Distribute Exercise for Uranium Explosion (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = <0.1 km Maximum CEDE = >0.031 rem

Exercise: Uranium Explosion

- Page 5-23 illustrates the graphical output for a Uranium Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - Six kilograms of weapons-grade uranium (90% U-=235, 10% U-238) are involved in a one-point detonation of a weapon containing 35 pounds of high explosive. The sun is high in the sky, and the wind speed is 4 meters/second. Estimate the ground contamination and 50-year committed effective dose equivalents as a function of down-wind centerline distance.
- Step 1 From the HOTSPOT Main Menu: Type **D** Type N; type 90; press Enter Step 2 Natural Uranium? (Y/N) Specific Activity: $S = 6.21E^{-05}$ Ci/q? (Y/N) Step 3 Type Y Mass? Type 6 Step 4 Fraction = $2.00E^{-01}$? (Y/N) Step 5 Type Y Step 6 High Explosive, lb? Type 35 Conditions? Type 1 for sun HIGH in the sky. Step 7 Wind? Step 8 Type 4 (for 4 meters/second); press Enter Step 9 Type 1 at the Main Outputs Options Menu to view data table.
- **Step 10** Press **Enter** as desired to view more data.
- **Step 11** Type **2** to return to the Output Menu.
- Step 12 Type G (graphics).
- **Step 13** Type **3** to view Centerline 50-yr. CEDE vs. Distance.
- **Step 14** Type **1** to select COLOR.
- **Step 15** Type **1** to enter downwind plotting range.

The result is the graph shown on the previous page of this manual.

Lesson 6 Uranium Fire Code E

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 6 – Uranium Fire, Code E

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, trainees will be able to model a uranium

fire involving released material, using the Uranium Fire Code E Atmospheric Dispersion Model of the HOTSPOT Health Physics

program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Uranium Fire Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Uranium Fire output (tabular and graphical)
 - Given mock data, generate Uranium Fire output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 6–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




6#1

- At the end of this lesson, students will be able to model a uranium fire involving released material, using the Uranium Fire Code E Atmospheric Dispersion Model.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Uranium Fire Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Uranium Fire output (tables and graphs)
 - Given mock data, generate Uranium Fire output (tables and graphs)

Graphical Output and Assumptions—Uranium Fire



6-#2

- Have students refer to Page 6-3, graphical output for the Uranium Fire incident.
- Discuss the assumptions concerning the Uranium Fire incident.

Reference

Graphical Output and Assumptions—Uranium Fire

- Review Page 6-3, graphical output for the Uranium Fire Atmospheric Dispersion Model derived from HOTSPOT.
- This example is based on the following assumptions:
 - The default respirable fraction of the total uranium involved in the fire that is released is 5x10⁻⁴ (0.05 %). The respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD) of 1 micrometer (see User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1 micrometer AMAD particle size distribution.
 - The effective release height is determined using the methodology contained in the "Fuel Fire" section of Appendix A. Once the effective release height is determined, the radius of the final bent-over plume is set equal to 60% of the effective release height (Hanna, 1982). An upwind virtual point source, which results in an initial σ_y and σ_z equal to 50% of the plume radius at the origin (i.e., plume radius = 2), is used to model the fire scenario.
 - Deposition velocity is 1 cm/sec.
 - Specific activity, S (Ci/g), as a function of U-235 enrichment is (Alexander, 1974)

```
S = (0.4 + 0.38E + 0.0034E^2)(10^{-6})
where E = percent enrichment.
```

This equation includes the contribution from U-234.

- Inhalation class is Y.
- Standard-person breathing rate is 1.2 cubic meters/hour.
- 100 kilograms of uranium (95% U-238, 5% U-235) being used in an isotope separation experiment are involved in a significant building fire (Heat Emission = 1x10⁷ calories/sec, effective radius of building fire is 50 meters). The sun has set, the wind speed is approximately 9 meters/second, and the ambient air temperature is 20 degrees C. The nearest occupied location is at a downwind distance of 0.5 kilometer. What is the maximum expected 50-year committed effective dose equivalent for this location?

Code Description: Uranium Fire

HOTSPOT 7.0 URANIUM FIRE

RADIONUCLIDE: URANIUM Inhalation Class: Y SPECIFIC ACTIVITY: 2.38E-06 Ci/g

SOURCE TERM : 1.0E+02 kg RELEASE FRACTION : 5.00E-04

HEAT EMISSION : 1.0E+07 cal/s RELEASE RADIUS : 50.0 m

EFFECTIVE RELEASE HEIGHT: 28.0 m

WIND SPEED (h=2 m): 9.0 m/s
STABILITY CLASS : D

RECEPTOR HEIGHT : 0.0 m
SAMPLE TIME : 10.000 min
MAXIMUM DOSE DISTANCE : 0.1 km

AVERAGE WINDSPEED: 13.4 m/s
DEPOSITION VELOCITY : 1.00 cm/s
INVERSION LAYER HEIGHT : NONE
MAXIMUM CEDE : 7.5E-05 rem

6-#3

Notes:

 Describe the code used to derive the Uranium Fire Atmospheric Dispersion Model illustrated in this lesson.

Code Description: Uranium Fire

• Code description — Study the table on page 6-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|---------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | I: General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: General Fire |
| | | | | Q: QUIT |

Enter Selection 6-#4

- Describe the steps involved to model the uranium fire incident.
- Explain that students should use the Reference page for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code E (Uranium Fire) from the HOTSPOT Main Menu.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- Effective Release Height—Explain the conditions under which the students would select 1, 2, or 3 from the Effective Release Height menu.
- Heat Emission— Define "heat emissions."
- Release Radius—Explain that the release radius is the effective radius of the fire, e.g., radius of burning fuel pool.
- Ambient Air Temperature—Define "ambient air temperature."
- Natural Uranium (Y/N)—Tell students this incident does not involve natural uranium; they must enter the percent U-235 by typing the number 5.

- Select Uranium Fire from the HOTSPOT Main Menu.
- Step 1 Type E
- Result The Effective Release Height menu appears:

1: Fire - You enter Effective Release Height.


2: Fire - HOTSPOT calculates Effective Release Height using input fuel and burn duration.

 Fire – HOTSPOT calculates Effective Release Height using input Heat Emission (calories per second).

- **Step 2** Type **3**
- Heat Emission?
- **Step 3** Type **1E7**
- Release Radius = 10 m? (Y/N)
- Step 4 Type N; type 50; press Enter
- Ambient Air Temperature?
- Step 5 Type Y
- Natural Uranium? (Y/N)

Enter percent U-235, and push Enter.

• Step 6 Type N; type 5; press Enter



6-#5

- Specific Activity = 2.38E-06 Ci/g?—This is the default weapons-grade value; explain alpha specific activity to the students.
- MASS (U), kg?—Explain that students must enter the total quantity of uranium involved in the fire (kilograms).
- Fraction = 5.000E–04?—Explain the concept of "fraction of the entered activity."

Specific Activity = 2.38E⁻⁰⁶ Ci/g (Y/N)?

Enter "Y" to accept the default weapons-grade value, or "N" if you wish to enter a new value.

- **Step 7** Type **Y**
- MASS, (U), kg?

Enter the total quantity of uranium involved in the explosion (kilograms), and push Enter.

- Step 8 Type 100; press Enter
- $F = 2.000E^{-01}$?

F is the fraction of entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

• Step 9 Type Y

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

6-#6

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 3 indicates the correct meteorological condition (NIGHT).

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 10** Type **3** to indicate meteorological condition (NIGHT).

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 - 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

6-#7

- Wind—Refer students to the Wind screen display.
- Explain the Plume Rise Summary Information table.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 11** Type **9**

Press the **Enter** key.

• Result The Plume Rise Summary Information table appears.

Plume Rise Summary Information

Heat Emission: 1.0E+07 calories/ second
Buoyancy Flux: 3.7E+02 meter^4/ second^3
Ambient Air Temp.: 20.0 degrees centigrade

Release Radius: 50.0 meters

Average Wind Speed.: 13.4 meters/ second

Effective Release Height: 28 meters

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- P: Plume Rise
- R: Review Plume Rise Data
- T: Sample Time
- Q: Enter to Main HOTSPOT Menu.

6-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 12 Type 1 to view data tables.
- Step 13 Press Enter view more data.

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- Output Option Number Menu
- 1: Enter a new Downwind Distance.
- 2: Return to Output Menu.
- Q: Return to Main HOTSPOT Menu.

6-#9

Notes:

• Explain that students must type 2 at the Output Option Number Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- **Step 14** Type **2** at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- P: Plume Rise
- R: Review Plume Rise Data
- T: Sample Time
- Q: Enter to Main HOTSPOT Menu.

6-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident.

- Option G—Graphics
- **Step 15** Type **G** for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: Centerline 50-yr. CEDE vs. Distance

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

6-#11

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color/Monochrome—Have students type the number 1 or 2.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results.

- **Step 16** Type **3** to view Centerline 50-yr. CEDE vs. Distance graph.
- Result The following selection box appears:
 - 1: COLOR
 - 2: MONOCHROME / LCD
- Step 17 Type 2 for monochrome, or type 1 for color.
- Result The following selection box appears:


DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km

- **Step 18** Type **1**; the result is a graph.
- Print (if you have printer capability).
- **Step 19** Press **P** to print the graph.

Exercise 6-1: Uranium Fire

• Exercise (Uranium: U-238, U235)



6-#12

- Distribute Exercise for Uranium Fire (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = 2.1 km Maximum CEDE = 7.9E-07 rem

Exercise 6-1: Uranium Fire

- Review the graphical output for this exercise (Uranium Fire Atmospheric Dispersion Model derived from HOTSPOT).
- The example for this exercise is based on the following assumptions:
 - Sixty kilograms of uranium (95% U-=238, 5% U-235) are involved in a significant building fire (Heat Emission = $3x10^7$ calories/sec, effective radius of building fire is 10 meters). It is a cloudy day, the wind speed is 10 meters/second, and the ambient air temperature is 16 degrees C. Estimate the ground contamination and 50-year committed effective dose equivalents as a function of down-wind centerline distance.
- From the HOTSPOT Main Menu: Type E Step 1 Step 2 Effective Release Height? Type 3 Step 3 Heat Emissions? Type **3E7** Release Radius = 10 m? (Y/N)Step 4 Type Y Ambient Air Temperature? Type N; type 16; press Enter Step 5 Natural Uranium? (Y/N) Type **N**; type **5**; press **Enter** Step 6 Specific Activity: $S = 2.38E^{-06}$ Ci/g? (Y/N) Step 7 Type Y Type **60**; press **Enter** Step 8 Mass (U), kg
- Fraction = $5.000E^{-04}$? (Y/N) Type Y Step 9
- Step 10 Conditions? Type 2 for cloudy day.
- Wind? Type **10** (for 10 meters/second); press **Enter** Step 11
- Result The Plume Rise Summary Information table appears.
- Type 1 at the Main Outputs Options Menu to view data Step 12 table.
- Step 13 Press **Enter** as desired to view more data.
- Step 14 Type 2 to return to the Output Menu.
- Step 15 Type **G** (graphics).
- Step 16 Type **3** to view Centerline 50-yr. CEDE vs. Distance.
- Step 17 Type 1 to select COLOR.
- Step 18 Type 1 to enter downwind plotting range.

The result is the graph shown on the previous page of this manual.

Lesson 7 Tritium Release Code T

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 7 – Tritium Release, Code T

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a tritium

release, using the Tritium Release Code T Atmospheric Dispersion

Model of the HOTSPOT Health Physics program.

Enabling:

• At the end of this lesson, students should be able to:

- Describe the graphical output for a Tritium Release Atmospheric Dispersion Model
- Explain the assumptions involved in deriving Tritium Release output (tabular and graphical)
- Given mock data, generate Tritium Release output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 7–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives



7-#1


- At the end of this lesson, students will be able to model a tritium release, using the Tritium Release Code T Atmospheric Dispersion Models.
- Explain the Lesson Objectives.

_____ Reference

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Tritium Release Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Tritium Release output (tables and graphs)
 - Given mock data, generate Tritium Release output (tables and graphs) using HOTSPOT

Graphical Output and Assumptions—Tritium Release



7-#2

- Have students refer to Page 7-3, graphical output for the Tritium Release incident.
- Discuss the assumptions concerning the Tritium Release incident.

Reference

Graphical Output and Assumptions—Tritium Release

- Review the graphical output for a Tritium Release Atmospheric Dispersion Model derived from HOTSPOT.
- This example is based on the following assumptions:
 - 50-year committed effective dose equivalent (rem-m3)/(Ci-sec):

TRITIATED WATER:

In the HOTSPOT Codes, it is assumed that 2/3 of the CEDE is due to inhalation and 1/3 of the CEDE is due to absorption through the intact skin (ICRP 30 Part 1, 1978, p 65).

CEDE : = 0.031 (0.021 inhalation) + 0.010 absorption)

ELEMENTAL TRITIUM:

CEDE: 1.2 x 10⁻⁶ LUNG: 1.0 x 10⁻⁵

— 30,000 curies of HTO are released from a 30-meter stack. The wind speed is 1 meter/second; on a cloudy day. What distance is associated with the maximum 50-year committed effective dose equivalent to an individual remaining at this location throughout the release?

Code Description: Tritium Release

HOTSPOT 7.0 TRITIUM RELEASE **TOTAL TRITIUM RELEASE:** 3.0E+04 curies 100.000 % TRITIUM OXIDE Dose Results Include Skin Absorption EFFECTIVE RELEASE HEIGHT: WIND SPEED (h=2 m): 1.0 m/s WIND SPEED (h=H-eff): 1.2 m/s STABILITY CLASS DEPOSITION VELOCITY : 0.0E+00 cm/s RECEPTOR HEIGHT NONE INVERSION LAYER HEIGHT: SAMPLE TIME 10.0 min MAXIMUM DOSE DISTANCE : 0.17 km MAXIMUM CEDE : 0.151 rem Plume Centerline 0.10 km D = 0.20 km D = 0.50 km 1.8E+00 (Ci-s)/m^3 CHI = CHI = 4.8E+00 (Ci-s)/m^3 CHI = 1.5E+00 (Ci-s)/m^3 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: **EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT** 5.6E-02 rem **EQUIVALENT** 1.5E-01 rem **EQUIVALENT** 4.6E-02 rem D = D = D = 5.00 km 1.00 km 2.00 km CHI = 4.2E-01 (Ci-s)/m^3 CHI = 1.1E-01 (Ci-s)/m^3 CHI = 2.0E-02 (Ci-s)/m^3 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: **EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT** 1.3E-02 rem **EQUIVALENT** 3.5E-03 rem **EQUIVALENT** 6.2E-04 rem

7-#3

Notes:

 Describe the code used to derive the Tritium Release Atmospheric Dispersion Model illustrated in this lesson. Reference Reference

Code Description: Tritium Release

• Code description — Study the table on page 7-5.

HOTSPOT Health Physics Codes VERSION 7.01 HAZARDS CONTROL DEPARTMENT LAWRENCE LIVERMORE NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: | Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|----|------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: | Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | l: | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: | Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: | General Fire |
| | | | | | Q: QUIT |

Enter Selection

7-#4

- Describe the steps involved in using HOTSPOT to model the incident involving a tritium release.
- Explain that the students should use the Reference page for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code T (Tritium Release) from the HOTSPOT Main Menu.
- Curies—Tell students to enter the total tritium release (curies).
- Tritiated Water—Have students enter the percent of the total tritium released in the form of tritiated water; in this example, it is 100%.
- Effective Release Height—Explain the conditions under which the students would select 1, 2, or 3 from the Effective Release Height menu; in this example, it is 30 meters.

Reference

Demonstration: Tritium Release

• Select Tritium Release from the HOTSPOT Main Menu.

• Step 1 Type T

• Curies?

Enter the total tritium release (curies), and push Enter.

• Step 2 Type 30000; press Enter

Tritiated Water?

Enter percent (e. g., 50%) of the total tritium released in the form of tritiated water, and push Enter.

• Step 3 Type 100; press Enter

- Effective Release Height?
- **Step 4** Type **30**

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

7-#5

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, type 2 to indicate cloudy meteorological condition.

Reference

Demonstration: Tritium Release

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• **Step 5** Type **2** to indicate meteorological condition (cloudy day).

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

7-#6

Notes:

• Wind—Refer students to the Wind screen display.

Reference

Demonstration: Tritium Release

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 6** Type **1**

Press the **Enter** key.

Main Output Options Menu

Main Output Options Menu

| 1: SCREEN | Output | Default | Distances |
|--------------|--------|-----------|-----------|
| 2: SCREEN | Output | You Enter | Distances |
| 3: PRINTER | Output | Default | Distances |
| 4: PRINTER | Output | You Enter | Distances |
| 5: DISK FILE | Output | Default | Distances |
| 6: DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Enter to Main HOTSPOT Menu.

7-#7

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

Reference

Demonstration: Tritium Release

- Main Outputs Options Menu
- Screen output
- Step 7 Type 1 to view data tables.

Press Enter view more data.

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

• Look at the Output Option Number Menu.

- Output Option Number Menu
- 1: Enter a new Downwind Distance.
- 2: Return to Output Menu.
- Q: Return to Main HOTSPOT Menu.

7-#8

Notes:

• Explain that students must type 2 at the Output Option Number Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- Step 8 Type 2 at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Enter to Main HOTSPOT Menu.

7-#9

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident.

- Option G—Graphics
- Step 9 Type G for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

7-#10

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color/Monochrome—Have students type the number 1 for COLOR.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results.

- **Step 10** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

- **Step 11** Type **1** for color monitor.
- Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


• **Step 12** Type **1**

The result is a graph.

- Print (if you have printer capability).
- **Step 13** Press **P** to print the graph.

Exercise 7-1: Tritium Release

• Exercise (Tritium Release)



7-#11

- Distribute Exercise for Tritium Release.
- Display Overhead.
- Explain that students may consult Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = 0.26 km Maximum CEDE = 0.328 rem

Reference

Exercise 7-1: Tritium Release

- Review the graphical output for this exercise (Tritium Release Atmospheric Dispersion Model derived from HOTSPOT).
- The example for this exercise is based on the following assumptions:
 - 160,000 curies of HTO are released from a 20-meter stack. the wind speed is 4 meters/second, and the sun has set. What distance is associated with the maximum 50-year committed effective dose equivalent to an individual remaining at this location throughout the release?

| • | Step 1 | From the HOTSPOT Main Menu, select T |
|---|---------|---|
| • | Step 2 | Total Tritium Released? Type 160,000 ; press Enter |
| • | Step 3 | Percent Tritiated Water? Type 100 ; press Enter |
| • | Step 4 | Effective Release Height? Type 20; press Enter |
| • | Step 5 | Condition? Type 3 (for NIGHT). |
| • | Step 6 | Wind? Type 4 (for 4 meters/second); press Enter |
| • | Step 7 | Type 1 at the Main Outputs Options Menu to view data table; press Enter as desired to view more data. |
| • | Step 8 | Type 1 at the Outputs Option Number Menu to enter downwind distance. |
| • | Step 9 | Type 2 to return to the Output Menu. |
| • | Step 10 | Type G (graphics). |
| • | Step 11 | Type 3 to view Centerline 50-yr. CEDE vs. Distance. |
| • | Step 12 | Type 2 to select MONOCHROME/LCD. |
| • | Step 13 | Type 1 to enter downwind plotting range. |

The result is the graph shown on the previous page of this manual.

Lesson 8 Nuclear Explosion Code F

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 8 – Nuclear Explosion, Code F

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a general

plume of released material, using the Nuclear Explosion Code F Air Dispersion Model of the HOTSPOT Health Physics Codes program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a Nuclear Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving Nuclear Explosion output (tabular and graphical)
 - Given mock data, generate Nuclear Explosion output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 8–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives



8-#1

- At the end of this lesson, students will be able to model a nuclear explosion involving released material, using the Nuclear Explosion Code F Atmospheric Dispersion Model of the HOTSPOT Health Physics Codes program.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Explain the assumptions involved in estimating the effects of a surfaceburst nuclear explosion.
 - Given mock data, generate Nuclear Explosion output.

Assumptions—Nuclear Explosion

SURFACE-BURST NUCLEAR DETONATION

YIELD: 1.00 kilotons
EFFECTIVE WIND SPEED: 15.00 mph
BLAST DATA ARE MAXIMUM OVERPRESSURE

COLOR CODE: BLAST RADIATION THERMAL

>30 psi >400 rad >3rd degree burns >5 psi >25 rad >2nd degree burns

NOTE: Temporary flash blindness can occur at 0.0001 cal/cm² and retinal burns at approximately 0.2 cal/cm².

Push "Enter" to Continue with Data Output

Notes:


Discuss the assumptions concerning the Nuclear Explosion calculations

.

Assumptions—Nuclear Explosion

- This example is based on the following assumptions:
 - The Nuclear Explosion code estimates the effects of a surface-burst nuclear weapon, based on the information in *The Effects of Nuclear Weapons* by Samuel Glasstone and Philip J. Dolan (3rd. ed., U. S. Department of Defense and the U. S. Department of Energy, 1977). As Glasstone and Dolan state, the predictive data are not exact. Users are strongly urged to refer to the book for detailed discussions and limitations of the effects data (see following tables on blast effects).
 - The code estimates the maximum overpressure (psi), prompt neutron and gamma doses (rad), and the thermal radiation (cal/cm^{2),} as a function of radial distance from the point of detonation. For distances greater than 1 km, the following fallout prediction data are generated
 - Arrival time of fallout.
 - Reference dose rate at one hour post-detonation (H + 1).
 - Initial dose rate at actual cloud arrival time.
 - Integral dose from external ionizing radiation in first hour, day, etc., since detonation.
 - Fallout assumptions: default effective windspeed is 15 miles per hour with a wind shear of 15°.

- 1. The RBE for neutrons varies with the energy and type of injury. For the neutron energy spectrum of nuclear weapons, the RBE for acute radiation injury is close to 1.0. However, the RBE is significantly larger (4-10) for the occurrence of opacities of the lens of the eye, leukemia, and genetic changes.
- 2. Approximate thermal exposure required to produce skin burns for yields 20 kT (Fig. 8-4).
 - First degree 2 cal/cm².
 - Second degree 4 cal/cm².
 - Third degree 7 cal/cm².



Tentative criteria for direct (primary) blast effects in people from fast-rising, long-duration pressure pulses.

| Effect | Peak Pressure (psi) |
|------------------|--------------------------------|
| Lung damage: | |
| Threshold | 12(8–15) |
| Severe | 25(20–30) |
| Lethality: | |
| Threshold | 40(30–50) |
| 50 percent | 62(50–75) |
| 100 percent | 92(75–115) |
| Eardrum rupture: | 5 |
| Threshold | 15-20 (more than 20 years old) |
| 50 percent | 30-35 (less than 20-years old) |

Approximate radiant exposures for ignition of various materials.

| | | | | Ra | diant Ex (cal/cn | posure 1 ²) |
|--|---------------------------------|-----------------|-------------------------|----------|---------------------|----------------------------|
| Material | Weight (oz/yd ²) | Color | Effect on Material | 35 kt | 1.4 Mt | 20 Mt |
| Household Tinder Materials | | - | - | | | - |
| Newspaper, shredded | 2 | | Ignites | 4 | 6 | 11 |
| Newspaper, dark picture area | 2 | | Ignites | 5 | 7 | 12 |
| Newspaper, printed text area | 2 | _ | Ignites | 6 | 8 | 15 |
| Crepe paper | 1 | Green | Ignites | 6 | 9 | 16 |
| Kraft paper | 3 | Tan | Ignites | 10 | 13 | 20 |
| Bristol board, 3 ply | 10 | Dark | Ignites | 16 | 20 | 40 |
| Kraft paper carton, used (flat side) | 16 | Brown | Ignites | 16 | 20 | 40 |
| New bond typing paper | 2 | White | Ignites | 24 | 30 | 50 |
| Cotton rags | | Black | Ignites | 10 | 15 | 20 |
| Rayon rags | | Black | Ignites | 9 | 14 | 21 |
| Cotton string scrubbing mop (used) | | Gray | Ignites | 10 | 15 | 21 |
| Cotton string scrubbing mop (weathered) | | Cream | Ignites | 10 | 19 | 26 |
| Paper book matches, blue head exposed | | | Ignites | 11 | 14 | 20 |
| Excelsior, ponderosa pine | | Light yellow | Ignites | | 23 | 23 |
| Outdoor Tinder Materials | - | | - | - | | - |
| Dry rotted wood punk (fir) | | | Ignites | 4 | 6 | 11 |
| Deciduous leaves (beech) | | | Ignites | 4 | 6 | 8 |
| Fine grass (cheat) | | | Ignites | 5 | 8 | 10 |
| Coarse grass (sedge) | | | Ignites | 6 | 9 | 11 |
| Pine needles, brown (pnderosa) | | | Ignites | 10 | 16 | 21 |
| Construction Materials | - | | | - | • | - |
| Roll roofing, mineral surface | | | Ignites | | >34 | >116 |
| Roll roofing, smooth surface | | | Ignites | | 30 | 77 |
| Plywood, douglas fir | | | Flaming | 9 | 16 | 20 |
| | | | during | | | |
| | | | exposure | | | |
| Rubber, pale latex | | | • | 50 | 80 | 110 |
| Rubber, black | | | Ignites | 10 | 20 | 25 |
| | | | Ignites | | | |
| Other Materials | | | Du i | 4.5 | 00 | 40 |
| Aluminum aircrraft skin (0.020 in. thick) coated with 0.002 in. of | | | Blisters | 15 | 30 | 40 |
| standard white aircraft paint Cotton canvas sandbags, dry-filled | | | Failure | 10 | 18 | 32 |
| | | | | | | |
| Coral sand | | | Explodes (popcorning) | 15 | 27 | 47 |
| Siliceous sand | | | Explodes (popcorning | 11 | 19 | 35 |

Conditions of failure of overpressure sensitive elements.

| Structural Element | Failure | Peak Overpressure (psi) |
|---|--|-------------------------|
| Glass windows, large and small | Shattering usually, occasional frame failure | 0.5–1.0 |
| Corrugated asbestos siding | Shattering | 1.0-2.0 |
| Corrugated steel or aluminum paneling | Connection failure followed by buckling | 1.0–2.0 |
| Brick wall panel, 8- or 12-in. thick (not reinforced) | Shearing and flexure failures | 3.0–10.0 |
| Wood siding panels, standard house construction | Usually failure occurs at the main connections allowing a whole panel to be blown in | 1.0–2.0 |
| Concrete or cinder-block wall panels, 8- or 12-in. thick (not reinforced) | Shattering of the wall | 1.5–5.5 |

Example—Nuclear Explosion

 What are the prompt radiation effects from the surface detonation of a l-kt fission device? Assume the atmospheric visibility is 50 miles, and the effective wind speed is 15 mph.

Code Description: Nuclear Explosion

SURFACE-BURST NUCLEAR DETONATION

YIELD: 1.00 kt

EFFECTIVE WIND SPEED: 15.00 mph
BLAST DATA ARE MAXIMUM OVERPRESSURE

NOTE: Temporary flash blindness cn occur at 0.0001 cal/cm²

and retinal burns at 0.16 cal/cm²

| D = 0.10 km | | D = 0.20 km | | D = 0.50 km | |
|---|-----------------------------|--|-----------------------------|--|-----------------------------|
| BLAST | 1.1E+02 psi | BLAST | 2.3E+01 psi | BLAST | 4.1E+00 psi |
| NEUTRON | 1.2E+07 rad | NEUTRON | 1.1E+05 rad | NEUTRON | 1.8E+03 rad |
| GAMMA | 1.7E+04 rad | GAMMA | 9.1E+03 rad | GAMMA | 1.3E+03 rad |
| TOTAL | 1.2E+07 rad | TOTAL | 1.2E+05 rad | TOTAL | 3.1E+03 rad |
| THERMAL | 3.2E+02 cal/cm ² | THERMAL | 7.9E+01 cal/cm ² | THERMAL | 1.3E+01 cal/cm ² |
| D = 1.00 km | | D = 2.00 km | | D = 5.00 km | |
| BLAST | 1.5E+00 psi | BLAST | 6.3E-0.1 psi | BLAST | 2.6E-01 psi |
| NEUTRON | 4.4E+01 rad | NEUTRON | 1.1E-01 rad | | |
| GAMMA | 6.1E+01 rad | GAMMA | 5.0E-01 rad | | |
| TOTAL | 1.0E+02 rad | TOTAL | 6.1E-01 rad | | |
| THERMAL | 3.1E+00 cal/cm ² | THERMAL | 7.5E-01 cal/cm ² | THERMAL | 1.1E–01 cal/cm ² |
| FALLOUT | | FALLOUT | | FALLOUT | |
| ARRIVES IN | 0.04 hour | ARRIVES IN | 0.08 hour | ARRIVES IN | 0.21 hour |
| H+1: | 6.6E+03 rem/hr | H+1: | 2.1E+03 rem/hr | H+1: | 4.5E+02 rem/hr |
| INITIAL EXTERNAL AT CLOUD ARRIVA 3.0E+05 rem/hr DOSE IN FIRST: | | | | | |
| HOUR | 3.0E+04 rem | HOUR | 6.7E+03 rem | HOUR | 8.4E+02 rem |
| DAY | 4.5E+04 rem | DAY | 1.2E+04 rem | DAY | 1.9E+03 rem |
| WEEK | 5.1E+04 rem | WEEK | 1.3E+04 rem | WEEK | 2.3E+03 rem |
| MONTH | 5.4E+04 rem | MONTH | 1.4E+04 rem | MONTH | 2.5E+03 rem |
| YEAR | 5.7E+04 rem | YEAR | 1.5E+04 rem | YEAR | 2.7E+03 rem |
| 50 YEARS | 6.0E+04 rem | 50 YEARS | 1.6E+04 rem | 50 YEARS | 2.9E+03 rem |
| D = 1.00 km | | D = 2.00 km | | D = 5.00 km | |
| BLAST | 1.6E-01 psi | MINIMAL BLAST | 1.0E-01 psi | MINIMAL BLAST A | AND RAD |
| THERMAL | 2.4E-02 cal/cm ² | THERMAL | 4.4E-03 cal/cm ² | THERMAL | 2.8E-04 cal/cm ² |
| FALLOUT | | FALLOUT | | FALLOUT | |
| ARRIVES IN | 0.41 hour | ARRIVES IN | 0.83 hour | ARRIVES IN | 2.07 hour |
| H+1: | 1.4E+02 rem/hr | H+1: | 4.5E+01 rem/hr | H+1: | 3.0E+00 rem/hr |
| INITIAL EXTERNAL RATE AT CLOUD ARRIVAL TIME IS 4.1E+02 rem/hr DOSE IN FIRST: | | INITIAL EXTERNA CLOUD ARRIVAL 5.6E+01 rem/hr DOSE IN FIRST: | | INITIAL EXTERNA CLOUD ARRIVAL 1.3E+00 rem/hr DOSE IN FIRST: | |
| HOUR | 1.4E+02 rem | HOUR | 8.6E+00 rem | HOUR | 0.0E+00 rem |
| DAY | 4.7E+02 rem | DAY | 1.1E+02 rem | DAY | 5.0E+00 rem |
| WEEK | 5.9E+02 rem | WEEK | 1.5E+02 rem | WEEK | 7.6E+00 rem |
| MONTH | 6.6E+02 rem | MONTH | 1.7E+02 rem | MONTH | 9.0E+00 rem |
| YEAR | 7.3E+02 rem | YEAR | 2.0E+02 rem | YEAR | 1.1E+01 rem |
| 50 YEARS | 7.9E+02 rem | 50 YEARS | 2.2E+02 rem | 50 YEARS | 1.2E+01 rem |

8-#2

Notes:

 Describe the code used to derive the Nuclear Explosion Atmospheric Dispersion Model discussed in this lesson.

Code Description: Nuclear Explosion

Code description — Study the table on page 8-9.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| _ | | | | | |
|----|--------------------------|----|---------------------------------------|------|------------------------|
| A: | Plutonium Explosion | B: | Plutonium Fire | C: F | Plutonium Resuspension |
| D: | Uranium Explosion | E | Uranium Fire | F: N | luclear Explosion |
| G: | Radiation Workplace | H: | General Plume | l: G | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | Т: Т | ritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: G | General Fire |
| | | | | | Q: QUIT |

Enter Selection

8-#3

- Describe the steps involved in using HOTSPOT to model a Nuclear Explosion incident.
- Explain that the students should use the reference for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code F (Nuclear Explosion) from the HOTSPOT Main Menu.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- Effective wind speed.
- Atmospheric visibility.

- Select Nuclear Explosion from the HOTSPOT Main Menu.
- **Step 1** Type **F**
- YIELD-kt

Enter the yield (kilotons), and push Enter.

- Step 2 Type 1; press Enter
- Effective wind speed


Default EFFECTIVE WIND SPEED is 15 mph. Do you want to enter a different value? (Y/N) DEFAULT = N

- Step 4 Type N
- Atmospheric visibility

Choose the appropriate atmospheric visibility from the following menu—Enter a LETTER, and push Enter.

| A: | 20 km | (12 miles) | |
|----|-------|------------|--|
| B: | 40 km | (25 miles) | |
| C: | 80 km | (50 miles) | |

• Step 5 Type C



8-#4

Notes:

• Explains the Output options

Output options

Enter the appropriate Output option Number from the following menu:

| 1: | SCREEN | Output | _ | Default Distances |
|----|---------------|-----------|------|---------------------|
| 2: | SCREEN | Output | _ | You Enter Distances |
| 3: | PRINTER | Output | | Default Distances |
| 4: | PRINTER | Output | _ | You Enter Distances |
| 5: | START | OVER | | Enter a new YIELD |
| Q: | Return to Mai | n HOTSPOT | Menu | |

Step 6 Type I

SURFACE-BURST NUCLEAR DETONATION

YIELD: 1.00 kilotons
EFFECTIVE WIND SPEED: 15.00 mph
BLAST DATA ARE MAXIMUM OVERPRESSURE

COLOR CODE: BLAST RADIATION THERMAL >30 psi >400 rad >3rd degree burns >5 psi >25 rad >2nd degree burns

NOTE: Temporary flash blindness can occur at 0.0001 cal/cm² and retinal burns at approximately 0.2 cal/cm².

Push "Enter" to Continue with Data Output

- Step 7 Press Enter
- Output Option Number Menu

Enter the appropriate Output option Number from the following menu

- 1: Enter a new Distance
- 2: Return to Output Menu
- Q: Return to Main HOTSPOT Menu
- Step 8 Type 1, 2, or Q.

Exercise 8-1: Nuclear Explosion

Exercise

```
D = 3.0 \text{ km}
Blast
            1.3E+00 psi
Neutron
            1.2E-02 rad
            2.4E-01 rad
Gamma
Total
            2.5E-01 rad
            3.9E+00 cal/cm^2
Thermal
Fallout arrive in 0.07 Hour
            1.6E+04 rem/hr
H+1:
Initial External Rate At Cloud Arrival Time:
                                           3.7E+05 rem/hr
Dose in First:
Hour
            5.5E+04 rem
            9.4E+04 rem
Day
Week
           1.1E+05 rem
Month
            1.2E+05 rem
Year
            1.2E+05 rem
50-Years
            1.3E+05 rem
Enter Distance, km, and push "Enter"
```

8-#5

- Distribute Exercise for Nuclear Explosion.
- Display Overhead.
- Explain that students may consult the Reference page if they wish.

Exercise 8-1: Nuclear Explosion

- Page 8-15 illustrates the output for a Nuclear Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - What are the prompt radiation effects at a distance of 3 km from a surface detonation of a 20-kt fission device?
 - Assume visibility is only 20 miles and the effective windspeed is 25 mph.
- Step 1 From the HOTSPOT Main Menu, select F
- Step 2 YIELD-kt? Type 20; press Enter
- Step 3 Type Y
- Step 4 Enter 25; press Enter
- Step 5 Type A
- **Step 6** Distances? Type **2** (You enter distances)
- Step 7 Type 3; press Enter

The result is the table shown on the previous page of this manual.

Lesson 9 General Plume Code H

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 9 – General Plume, Code H

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a general

plume of released material, using the General Plume Code H Air Dispersion Model of the HOTSPOT Health Physics Codes program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Plume Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Plume output (tabular and graphical)
 - Given mock data, generate General Plume output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 9–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




9-#1

- At the end of this lesson, students will be able to model a general plume of released material, using the General Plume Code H Air Dispersion Model of the HOTSPOT Health Physics Codes program (HOTSPOT).
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Plume Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Plume output (tabular and graphical)
 - Given mock data, generate General Plume output (tabular and graphical)

Graphical Output and Assumptions—General Plume



9-#2

- Have students refer to page 9-3, General Plume: Graphical Output.
- Discuss the assumptions concerning the General Plume incident, as described on the Reference page.

Graphical Output and Assumptions—General Plume

- Page 9-3 illustrates graphical output for a General Plume Air Dispersion Model derived from the HOTSPOT program.
- This example is based on the following assumptions:
 - The default respirable fraction of the total material involved in the release is dependent upon the type of material input, e.g., 1.00 for noble gases, 0.0005 for plutonium, etc. For non-noble gas radionuclides, the respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD) of 1 micrometer (see User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1μm AMAD particle size distribution.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - The wind is from the east at 1 meter/second on a sunny day.
- The students' goal is to estimate the dose commitments from a release of 20,000 curies of krypton-85 from a 10 meter stack.

Code Description: General Plume

HOTSPOT 7.01 GENERAL PLUME RADIONUCLIDE: KR-85 Inhalation Class: N/A HALFLIFE: 10.720 years SOURCE TERM : 2.0E+04 Ci RELEASE FRACTION: 1.00E+00 FILTER EFFICIENCY: 0.000000 % EFFECTIVE RELEASE HEIGHT: 10.00 m WIND SPEED (h=2 m): 1.0 m/s WIND SPEED (h=H-eff): 1.1 m/s STABILITY CLASS : A DEPOSITION VELOCITY : 0.0E+00 cm/s RECEPTOR HEIGHT : 0.0 m INVERSION LAYER HEIGHT : 5000.0 m : 10.000 min SAMPLE TIME MAXIMUM DOSE DISTANCE : < 0.1 km MAXIMUM CEDE : > 5.4E-03 rem Plume Centerline $D = 0.10 \, \text{km}$ $D = 0.20 \, \text{km}$ $D = 0.50 \, \text{km}$ CHI = 1.1E+01 (Ci-s)/m^3 CHI = 3.2E+00 (Ci-s)/m^3 $CHI = 5.3E-01 (Ci-s)/m^3$ 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 5.4E-03 rem EQUIVALENT 1.5E-03 rem EQUIVALENT 2.5E-04 rem $D = 1.00 \, \text{km}$ $D = 2.00 \, \text{km}$ $D = 5.00 \, \text{km}$ CHI = 1.4E-01 (Ci-s)/m^3 CHI = 3.5E-02 (Ci-s)/m^3 $CHI = 6.3E-03 (Ci-s)/m^3$ 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 1.7E-05 rem EQUIVALENT 6.4E-05 rem EQUIVALENT 3.0E-06 rem

D = 10.00 kmD = 20.00 kmD = 50.00 km

CHI = 1.8E-03 (Ci-s)/m^3 CHI = 5.6E-04 (Ci-s)/m^3 $CHI = 1.3E-04 (Ci-s)/m^3$

50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: ----------

EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE

EQUIVALENT 8.7E-07 rem EQUIVALENT 2.7E-07 rem EQUIVALENT 6.0E-08 rem

9-#3

Notes:

Describe the code used to derive the General Plume Atmospheric Dispersion Model illustrated in this lesson.

Code Description: General Plume

• Code description — Study the table on page 9-5.

HOTSPOT Health Physics Codes VERSION 7.01 HAZARDS CONTROL DEPARTMENT LAWRENCE LIVERMORE NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: | Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|----|------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: | Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | l: | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: | Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: | General Fire |
| | | | | | Q: QUIT |

Enter Selection


9-#4

- Describe the steps involved in using HOTSPOT to model the incident involving the release of krypton-85.
- Explain that the students should use the Reference pages for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident; in this example, the students must select Code H (General Plume) from the HOTSPOT Main Menu.
- Nuclide—What nuclide is involved in this incident? Tell the students that this example involves the release of krypton–85 (KR–85).
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.

Demonstration: General Plume

- Code?
- **Step 1** Type **H** to select General Plume from the HOTSPOT Main Menu.
- Nuclide?
- **Step 2** Type **KR–85** (always in the form XX–NN, where XX represents the letters representing the nuclide name, and where NN represents the nuclide number).

Press the **Enter** key.



9-#5

- Curies—How many curies were released from the stack? The answer is 20,000. Remind the students to review the Assumptions on page 9-4 of this lesson.
- F = 1.000E+00? (Y/N)—Explain that the default respiration fraction of the total material involved in the release is dependent upon the type of material and that typing Y means that you accept the default.

- Curies? How many curies were released in this example incident?
- Step 3 Enter 20,000


Press the **Enter** key.

• F = 1.000E + 00? (Y/N)

F is the fraction of the entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

• Step 4 Enter Y to accept the default value.



9-#6

- Filter = 0%? (Y/N)—Explain the mitigation factor.
- HEIGHT—Explain the effective release height.

Filter = 0%? (Y/N)

Filter is the mitigation factor for the entered nuclide. The 0 is the default value, i.e., none of the nuclide entering the "FILTER" will be trapped. EXAMPLES:

FILTER = 99.97% for a single HEPA filter FILTER = 99.999991% for a two-stage HEPA

- Step 5 Enter Y to accept the default value.
- HEIGHT?

Enter the effective release height, in meters, and press the Enter key.

• **Step 6** Enter **10**

Press the **Enter** key.

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

- A: A stability Very unstable
- B: B stability Moderately unstable
- C: C stability Slightly unstable
- D: D stability Neutral
- E: E stability Slightly stable
- F: F stability Moderately stable
- G: G stability Special nighttime, low wind

Enter selection

9-#7

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 1 indicates the correct meteorological condition.

- Meteorological Conditions
 Enter a number or a letter to indicate appropriate meteorological condition.
- **Step 7** Type **1**

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-----------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light air | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 - 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 - 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 - 75 | 28 – 34 |
| hurricane | • | > 75 | > 34 |

9-#8

Notes:

• Wind—Refer students to the Wind screen display.

Demonstration: General Plume

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 8** Type **1**

Press the Return key.

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

G: GRAPHICS

C: Change DEFAULT CONTOUR SETTINGS

M: Change METEOROLOGICAL PARAMETERS and Release Height

Z: Change RECEPTOR HEIGHT (z)

D: Change DEPOSITION VELOCITY

O: Enable prompt for OFF AXIS Positions

I: INVERSION HEIGHT (Mixing Layer)

Q: Return to Main HOTSPOT Menu

T: Sample Time

Q: Return to Main HOTSPOT Menu

9-#9

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

Reference

Demonstration: General Plume

- Main Outputs Options Menu
- Screen output
- Step 9 Type 1 to view data tables.

Press **Return** to view more data.

Continue pressing **Return** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- 1: Enter a new Downwind Distance
- 2: Return to Output Menu
- Q: Return to Main HOTSPOT Menu

9-#10

- Explain that students may enter a new downwind distance by selecting option 1 from the Output Option Number Menu.
- Explain the results table.

- Output Option Number Menu
- **Step 10** Type **1** to enter a new distance.

The following message appears:

Enter Distance, km, and push "Enter." To enter an off-axis position (x, y), enter x y, e.g., 3 6 for x = 3 km and y = 6 km Push "Enter" without data entry to QUIT.

• **Step 11** Type **3 6** to enter an off-axis position.

The results table shows the following:

D = 3.00 km OFF-AXIS - Y = 6.00 km CHI = 7.7E-26 (Ci-s)/m^3 50-YR DOSE COMMITMENT EFFECTIVE DOSE EQUIVALENT 3.6E-29 rem

Press Return

• **Step 12** Type **2** at the Output Option Number Menu to return to the Main Output Options Menu.

Main Output Options Menu—Option G

Main Output Options Menu

- 1: SCREEN Output Default **Distances** Output You Enter 2: SCREEN **Distances** 3: PRINTER Output Default **Distances** 4: PRINTER Output You Enter **Distances** 5: DISK FILE Output Default Distances 6: DISK FILE Output You Enter **Distances**
- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- T: SAMPLE TIME
- Q: Return to Main HOTSPOT Menu.

9-#11

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident.

- Option G—Graphics
- **Step 13** Type G for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

9-#12

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color—Have students type the number 1.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as on page 9-3).

• **Step 14** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.

The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

• Step 15 Type 1 for color monitor.

The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


• **Step 16** Type **1**

The result is a graph.

- Print?
- **Step 17** Press **P** to print the graph (if you have printer capability).

Exercise 9-1: General Plume

• Exercise (I131)



9-#21

- Distribute Exercise for General Plume (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = 0.17 km Maximum CEDE = 1.8 rem

Reference

Exercise 9-1: General Plume

- Page 9-25 illustrates the graphical output for a General Plume Air Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - The default respirable fraction of the total material involved in the release is dependent upon the type of material input, e.g., 1.00 for noble gases, 0.0005 for plutonium, etc. For non-noble gas radionuclides, the respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD) of 1 micrometer (see Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1μm AMAD particle size distribution.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - The wind is from the east at 2 meter/second on a cloudy day.
- The students' goal is to estimate the dose commitments from a release of 1000 curies of iodine-131 from a 20 meter stack.

| • | Step 1 | From the HC | DTSPOT Main Menu, select H |
|---|---------|-----------------------------------|---|
| • | Step 2 | Nuclide? | Type I-131 |
| • | Step 3 | Curies? | Type 1000 |
| • | Step 4 | Fraction? | Type Y |
| • | Step 5 | Filter? | Type Y |
| • | Step 6 | Height? | Type 20 |
| • | Step 7 | Conditions? | Type 2 (for Cloudy). |
| • | Step 8 | Wind? | Type 2 (for 2 m/s); press Return |
| • | Step 9 | • • | e Main Outputs Options Menu to view data Enter as desired to view more data. |
| • | Step 10 | Type 1 at the downwind dis | e Outputs Option Number Menu to enter a new stance. |
| • | Step 11 | Type 4 7 to | enter an off-axis position. |
| • | Step 12 | Type 2 to ret | turn to the Output Menu. |
| • | Step 13 | Type G (grap | phics). |
| • | Step 14 | Type 3 to vie | ew Centerline 50-yr. CEDE vs. Distance. |
| • | Step 15 | Type 1 to se | lect COLOR. |
| • | Step 16 | Type 1 to en | ter downwind plotting range. |
| | | | |

The result is the graph shown on the previous page of this manual.

Lesson 10 General Explosion Code I

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 10 – General Explosion, Code I

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a general

explosion of released material, using the General Explosion Code I Atmospheric Dispersion Model of the HOTSPOT Health Physics

Codes program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Explosion output (tabular and graphical)
 - Given mock data, generate General Explosion output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 10–1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




10-#1

- At the end of this lesson, students will be able to model a general explosion of released material, using the General Explosion Code I Atmospheric Dispersion Model of the HOTSPOT Health Physics Codes program (HOTSPOT).
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to do the following:
 - Describe the graphical output for a General Explosion Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Explosion output (tables and graphs)
 - Given mock data, generate General Explosion output (tables and graphs)

Graphical Output and Assumptions—General Explosion



10-#2

- Have students refer to Page 10-3, General Explosion: Graphical Output.
- Discuss the assumptions concerning the General Explosion incident, as described on the Reference page.

Reference

Graphic Output and Assumptions—General Explosion

- Page 10-3 illustrates output for a General Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - The default respirable fraction of the total material involved in the explosion is dependent upon the type of material input, e.g., 1.00 for noble gases, 0.20 for plutonium, etc. For non-noble gas radionuclides, the respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD), of 1 micrometer (see User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1 micrometer AMAD particle size distribution.
 - For non-noble gas radionuclides, the deposition velocity of the non-respirable fraction (AMAD = 40 micron) is 8 cm/sec. The non-respirable fraction equals 1-f, where f is the respirable fraction. The non-respirable fraction is used for deposition estimates only, and does not contribute to the inhalation dose values.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - A vehicle, transporting 30 curies of iodine-131 is involved in a severe accident that results in the detonation of the vehicle's gas tank. The wind is from the west at 2 meters/second on a cloudy day. Assuming the release fraction is 1.0, estimate the radiation dose commitments downwind from this accident scene. NOTE: A conservative estimate of the TNT equivalent of an exploding vehicle gas tank is one pound.

Code Description: General Explosion

HOTSPOT 7.01 GENERAL EXPLOSION RADIONUCLIDE: I-131 Inhalation Class: D

HALFLIFE: 8.045 days SOURCE TERM : 3.0E+01 Ci RELEASE FRACTION: 1.00E+00 HIGH EXPLOSIVE : 1.0 lbs CLOUD TOP 76 m WIND SPEED (h=2 m): 2.0 m/s

STABILITY CLASS : C
RECEPTOR HEIGHT : 0.0 m
MAXIMUM DOSE DISTANCE : < 0.1 km

DEPOSITION VELOCITY : 1.00 cm/s
INVERSION LAYER HEIGHT : NONE
MAXIMUM CEDE : > 0.031 rem

Plume Centerline

 $D = 0.10 \, \text{km}$ $D = 0.20 \, \text{km}$

D = 0.50 kmDEP = 2.9E+01 uCi/m^2 CHI = 2.9E-03 (Ci-s)/m^3 DEP = 2.0E+01 uCi/m^2 CHI = 2.0E-03 (Ci-s)/m^3 $DEP = 8.3E+00 \text{ uCi/m}^2$ CHI = 8.3E-04 (Ci-s)/m^3

 50-YR DOSE COMMITMENT:
 50-YR DOSE COMMITMENT:
 50-YR DOSE COMMITMENT:

 THYROID 1.1E+00 rem
 THYROID 7.2E-01 rem
 THYROID 3.0E-01 rem

 EFFECTIVE DOSE
 EFFECTIVE DOSE
 EFFECTIVE DOSE
 -----THYROID 7.2E-01 rem
EFFECTIVE DOSE
EQUIVALENT 2.1E-02 rem EQUIVALENT 3.1E-02 rem EQUIVALENT 8.8E-03 rem

 $D = 1.00 \, \text{km}$ $D = 2.00 \, \text{km}$ $D = 5.00 \, \text{km}$

DEP = 3.2E+00 uCi/m^2 DEP = 1.0E+00 uCi/m^2 CHI = 3.2E-04 (Ci-s)/m^3 CHI = 1.0E-04 (Ci-s)/m^3 $DEP = 2.3E-01 \text{ uCi/m}^2$ $CHI = 2.3E-05 (Ci-s)/m^3$

50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: THYROID 1.2E-01 rem THYROID 3.8E-02 rem THYROID 8.5E-03 rem

EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 3.4E-03 rem EQUIVALENT 1.1E-03 rem EQUIVALENT 2.5E-04 rem

10-#3

Notes:

Describe the code used to derive the General Explosion Atmospheric Dispersion Model discussed in this lesson.

Code Description: General Explosion

• Code description — Study the table on page 10-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: | Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|----|------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: | Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | l: | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: | Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: | General Fire |
| | | | | | Q: QUIT |

Enter Selection

10-#4


- Describe the steps in using HOTSPOT to model the explosion incident involving I-131.
- Explain that the students should use the reference for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code I (General Explosion) from the HOTSPOT Main Menu.
- Nuclide—What nuclide is involved in this incident? Tell the students that this example involves iodine–131 (I–131).
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.

Reference

Demonstration: General Explosion

- Select General Explosion Atmospheric Dispersion Model from the HOTSPOT Main Menu.
- **Step 1** Type **I** to select General Explosion from the HOTSPOT Main Menu.
- Nuclide?
- **Step 2** Type **I-131** (always in the form XX-NN, where XX represents the letters representing the nuclide name, and where NN represents the nuclide number).

Press the **Enter** key.



10-#5

- Curies—How many curies were released in this explosion? The answer is 30. Remind the students to review the Assumptions on page 10-4 of this lesson.
- F = 1.000E+00? (Y/N)—Explain that the default respiration fraction of the total material involved in the explosion is dependent upon the type of material, and that typing "Y" means that they accept the default.

- Curies?
- Step 3 Enter 30


Press the **Enter** key.

• F = 1.000E + 00? (Y/N)

F is the fraction of the entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

Step 4 Enter Y to accept the default value.



10-#6

- High Explosive, lb?—Tell the students that they must enter the quantity of explosive (pounds)
- In this example, they must type 1.0 (for 1 pound) and press Enter

- High Explosive, lb?
- **Step 5** Type **1.0** for 1 pound.

Press the **Enter** key.

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

10-#7

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to Meteorological Conditions screen display (slide 10-7).
- In this example, the number 2 indicates the correct meteorological condition.

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• Step 6 Type 2 to indicate cloudy day.

Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

10#8

Notes:

• Wind—Refer students to the Wind screen display (slide 10-8).

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 7** Type **2**

Press the **Enter** key.

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Return to Main HOTSPOT Menu.

10-#9

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Return to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 8 Type 1 to view data tables.

Press **Return** to view more data.

Continue pressing **Return** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

- 1: Enter a new Downwind Distance
- 2: Return to Output Menu
- Q: Return to Main HOTSPOT Menu

10-#10

- Explain that students may enter a new downwind distance by selecting option 1 from the Output Option Number Menu.
- Explain the results table.

- Output Option Number Menu
- **Step 9** Type **1** to enter a new distance.

The following message appears:

Enter Distance, km, and push "Enter." To enter an off-axis position, (x, y), enter x y, e.g., 3 6 for x = 3 km and y = 6 km Push "Enter" w/o data entry to QUIT.

• **Step 10** Type **4 0.1** to enter an off-axis position.

The results table shows the following:

D = 4.00 kmOFF-AXIS – Y = 0.1 kmDEP = 3.2E- $01 \mu\text{Ci/m}^2$ CHI = 3.2E-05 (Ci–s)/m 3 50-YR DOSE COMMITMENT THYROID 1.2E-02 rem EFFECTIVE DOSE EQUIVALENT 3.4E-04 rem

• Step 11 Press Return

Type **2** at the Output Option Number Menu to return to the Output Menu.

Main Output Options Menu—Option G

Main Output Options Menu

| 1: SCRE | EN Output | Default | Distances |
|-----------|-------------|-----------|-----------|
| 2: SCRE | EN Output | You Enter | Distances |
| 3: PRINT | TER Output | Default | Distances |
| 4: PRINT | TER Output | You Enter | Distances |
| 5: DISK | FILE Output | Default | Distances |
| 6: DISK I | FILE Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Return to Main HOTSPOT Menu.

10-#11

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident's air dispersion model

- Option G—Graphics
- Step 11 Type G for Graphics.
- Result An Output option number menu appears.

Demonstration: General Explosion

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

10-#12

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color—Have students type the number 1 (for COLOR).
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as slide 10-2).

Demonstration: General Explosion

• **STEP 12** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.

The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


Type 1

The result is a graph.

Press **P** to print the graph (if you have printer capability).

Exercise 10-1: General Explosion

• Exercise (Am-241)



10-#13

- Distribute Exercise for General Explosion involving Am-241.
- Display Overhead.
- Explain that students may consult Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = <0.1 km Maximum CEDE = >3.6 rem

Reference

Exercise 10-1: General Explosion

- Page 10-25 illustrates the graphical output for a General Explosion Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - An explosion involving 5 curies of americium-241 in a liquid solution occurs at a research facility. It is estimated that the explosion is equivalent to 10 pounds of TNT. The wind is blowing at 3 meters/second on a sunny day. Assuming the respirable fraction is 0.20 (20%), estimate the radiation dose commitments downwind from this accident scene.
- Step 1 From the HOTSPOT Main Menu, select I
- Step 2 Nuclide? Type AM-241
- Step 3 Curies? Type 5; press Enter
- Step 4 Fraction? Type Y
- Step 5 High Explosive? Type 10; press Enter
- **Step 6** Conditions? Type **1** (for Sunny).
- Step 7 Wind? Type 3 (for 3 meters/second); press Return
- **Step 8** Type **1** at the Main Outputs Options Menu to view data table; press **Enter** as desired to view more data.
- **Step 9** Type **1** at the Outputs Option Number Menu to enter downwind distance.
- **Step 10** Type **2** to return to the Output Menu.
- **Step 11** Type **G** (graphics).
- **Step 12** Type **3** to view Centerline 50-yr. CEDE vs. Distance.
- Step 13 Type 1 to select COLOR.
- **Step 14** Type **1** to enter downwind plotting range.

The result is the graph shown on the previous page of this manual.

Lesson 11 General Fire Code N

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 11 - General Fire, Code N

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to model a general

fire involving released material, using the General Fire Code N Atmospheric Dispersion Model of the HOTSPOT Health Physics

program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Fire Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Fire output (tabular and graphical)
 - Given mock data, generate General Fire output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 11–1

Lesson Objectives




11-#1

- At the end of this lesson, students will be able to model a general fire involving released material, using the General Fire Code N Atmospheric Dispersion Model of the HOTSPOT Health Physics program.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Fire Atmospheric Dispersion Model.
 - Explain the assumptions involved in deriving General Fire output (tables and graphs).
 - Given mock date, generate General Fire output (tables and graphs).

Graphical Output and Assumptions—General Fire



11-#2

- Have students refer to Page 11-3, General Fire: Graphical Output.
- Discuss the assumptions involved in this incident, as described on the Reference page.

Reference

Graphic Output and Assumptions—General Fire

- Page 11-3 illustrates output for a General Fire Atmospheric Dispersion Model derived from HOTSPOT.
- This example is based on the following assumptions:
 - The default respirable fraction of the total material involved in the fire is dependent upon the type of material input, e.g., 1.00 for noble gases, 0.0005 for plutonium, etc. For non-noble gas radionuclides, the respirable fraction is defined as the fraction of the released material associated with an Activity Median Aerodynamic Diameter (AMAD), of 1 micrometer (See User Manual, Appendix A). The default ICRP-30 internal dosimetry conversion factors also assume a 1 micrometer AMAD particle size distribution.
 - The effective release height is determined using the methodology contained in the "Fuel Fire" section of Appendix A (User Manual). Once the effective release height is determined, the radius of the final bent-over plume is set equal to 60% of the effective release height (Hanna, 1982). An upwind virtual point source, which results in an initial σ_y and σ_z equal to 50% of the plume radius at the origin (i.e., plume radius = 2), is used to model the fire scenario.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - Fifty curies of americium-241 are involved in a laboratory fire. The effective radius of the fire is 20 meters. The sun is low in the sky, and the wind speed is approximately 4 meters/second. The observed cloud top of the plume is approximately 20 meters above the ground. Estimate the ground contamination and 50-year committed effective dose equivalents as a function of down-wind centerline distance.

Code Description: General Fire

HOTSPOT 7.01 GENERAL FIRE RADIONUCLIDE: AM-241 Inhalation Class: W HALFLIFE: 432.2 years SOURCE TERM : 5.0E+01 Ci RELEASE FRACTION: 5.00E-04 RELEASE RADIUS : 20.0 m EFFECTIVE RELEASE HEIGHT: 10.00 m WIND SPEED (h=2 m): 4.0 m/s WIND SPEED (h=H-eff): 4.7 m/s STABILITY CLASS : C DEPOSITION VELOCITY : 1.00 cm/s RECEPTOR HEIGHT : 0.0 m INVERSION LAYER HEIGHT: NONE SAMPLE TIME : 10.000 min MAXIMUM DOSE DISTANCE : < 0.1 km MAXIMUM CEDE :> 0.673 rem $D = 0.20 \, \text{km}$ $D = 0.10 \, \text{km}$ $D = 0.50 \, \text{km}$ DEP = 3.9E-02 uCi/m^2 $DEP = 1.9E-02 uCi/m^2$ $DEP = 5.3E-03 \text{ uCi/m}^2$ $CHI = 3.9E-06 (Ci-s)/m^3$ CHI = 1.9E-06 (Ci-s)/m^3 $CHI = 5.3E-07 (Ci-s)/m^3$ 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: SURFACE BONE 6.0E+00 rem SURFACE BONE 1.7E+00 rem SURFACE BONE 1.2E+01 rem RED MARROW 9.6E-01 rem RED MARROW 4.7E-01 rem RED MARROW 1.3E-01 rem LIVER 1.3E+00 rem
GONADS 7.7E-00 3.6E-01 rem 2.6E+00 rem LIVER LIVER LIVER GONADS 1.6E-01 rem GONADS 2.1E-02 rem EFFECTIVE DOSE EFFECTIVE DOSE **EFFECTIVE DOSE** EQUIVALENT 6.7E-01 rem EQUIVALENT 3.3E-01 rem EQUIVALENT 9.3E-02 rem $D = 1.00 \, \text{km}$ $D = 2.00 \, \text{km}$ $D = 5.00 \, \text{km}$ $DEP = 1.7E-03 uCi/m^2$ $DEP = 5.3E-04 \text{ uCi/m}^2$ DEP = 1.2E-04 uCi/m^2 CHI = 5.3E-08 (Ci-s)/m^3 CHI = 1.7E-07 (Ci-s)/m^3 $CHI = 1.2E-08 (Ci-s)/m^3$ 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: SURFACE BONE 5.3E-01 rem SURFACE BONE 1.6E-01 rem SURFACE BONE 3.6E-02 rem 2.9E-03 7.7E-03 rem GONADS RED MARROW 4.2E-02 rem RED MARROW 1.3E-02 rem RED MARROW 2.9E-03 rem LIVER 1.1E-01 rem
GONADS 6.8E-03 rem LIVER 3.5E-02 rem
GONADS 2.1E-03 rem LIVER LIVER 4.6E-04 rem EFFECTIVE DOSE **EFFECTIVE DOSE EFFECTIVE DOSE** EQUIVALENT 3.0E-02 rem EQUIVALENT 9.1E-03 rem EQUIVALENT 2.0E-03 rem

11-#3

Notes:

 Describe the code used to derive the General Fire Atmospheric Dispersion Model illustrated in this lesson.

Code Description: General Fire

• Code description — Study the table on page 11-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY

S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: | Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|----|------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: | Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | l: | General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: | Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: | General Fire |
| | | | | | Q: QUIT |

Enter Selection 4-#4

- Describe the steps involved in using HOTSPOT to model the incident where fifty curies of americium—241 are involved in a laboratory fire.
- Explain that the students should use the Reference page for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code N (General Fire) from the HOTSPOT Main Menu.
- Effective Release Height—Explain the conditions under which the students would select 1, 2, or 3 from the Effective Release Height menu.
- Release Radius—Explain that release radius is the effective radius of the fire. Tell the students to enter a value (in this example, it is 20 meters) rather than to accept the default.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.

Reference

Demonstration: General Fire

 Select General Fire Atmospheric Dispersion Model from the HOTSPOT Main Menu.

- Step 1 Type N to select General Fire from the HOTSPOT Main Menu.
- Result The Effective Release Height menu appears:

1: Fire -You enter Effective Release Height.

- 2: Fire HOTSPOT calculates Effective Release Height using input fuel and burn duration.
- Fire HOTSPOT calculates Effective Release Height using input Heat Emission (calories per second).
- **Step 2** Type **1**
- Result The Release Radius message appears:

Release Radius = 10 m? (Y/N) Release radius is the effective radius of the fire, e.g., radius of burning fuel pool. The default is 10 meters.


- Step 3 Type N
- Result The Enter Release Radius message appears:

Enter Release Radius (meters), and push Enter.

Note: Release Radius must be a value greater than 1 meter.

• **Step 4** Type **20**

Press the **Enter** key.



11-#5

- Nuclide— What nuclide is involved in this incident? Tell the students that this example involves americium—241 (am-241).
- Curies—How many curies were released in this explosion? The answer is 50. Remind the students to review the Assumptions on page 11-4 of this lesson.
- F = 1.000E+00? (Y/N)—Explain that the default respiration fraction of the total material involved in the release is dependent upon the type of material and that typing Y means that you accept the default.
- Height—Explain what is meant by effective release height.

- Nuclide?
- Step 5 Type am–241 (always in the form XX-NN, where XX represents the letters representing the nuclide name, and where NN represents the nuclide number).

Press the **Enter** key.

- Curies? Enter the total activity of the nuclide involved in the release.
- **Step 6** Enter **50**

Press the **Enter** key.

F = 1.000E+00? (Y/N)

F is the fraction of the entered activity released and dispersed into an AMAD of one micron.

Enter "Y" to accept the default value, or "N" if you wish to enter a new value.

- Step 7 Enter Y to accept the default value.
- Height? Enter the effective release height.

Note: If you are estimating the effective release height from an observation of the CLOUD TOP, input CLOUD TOP / 2, e.g., Effective Height = 0.5 * CLOUD TOP.

• **Step 8** Type **20** to enter the effective release height.

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

11-#6

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 2 indicates the correct meteorological condition (sun low in sky).

Meteorological Conditions

Enter a number or a letter to indicate appropriate meteorological conditions.

• Step 9 Type 2 to indicate sun low in sky.

• Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

11-#7

Notes:

• Wind—Refer students to the Wind screen display.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 10** Type **4**

Press the **Enter** key.

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- T: SAMPLE TIME
- Q: Enter to Main HOTSPOT Menu.

11-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data tables—The students must type 1 and press Enter to view the data tables.

- Main Outputs Options Menu
- Screen output
- Step 11 Type 1 to view data tables.

Press Enter view more data.

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

Output Option Number Menu

1: Enter a new Downwind Distance

2: Return to Output Menu

Q: Return to Main HOTSPOT Menu

11-#9

Notes:

 Explain that students must type 2 at the Output Option Number Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- Step 12 Type 2 at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS AND Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Enter to Main HOTSPOT Menu.

11-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident's air dispersion model.

- Option G—Graphics
- Step 13 Type G for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: GROUND DEPOSITION Contours
- 3: Centerline 50-yr. CEDE vs. Distance
- C: Change Graphics Output File Name

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

11-#11

- Output Option Number Menu
- Students may view Centerline 50-yr. CEDE vs. Distance graphical output by typing the number 3.
- Color—Have students type the number 1.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as on Page 11-3).

- **STEP 14** Type **3** to view Centerline 50-yr. CEDE vs. Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


Type 1

The result is a graph.

Press **P** to print the graph (if you have printer capability).

Exercise 11-1: General Fire

• Exercise (Cm-244)



11-#12

- Distribute Exercise for General Fire involving curium-244.
- Display Overhead.
- Explain that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = 1.8 km Maximum CEDE = 0.031 rem

Reference

Exercise 11-1: General Fire

- Page 11-23 illustrates the graphical output for a General Fire Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - An aircraft transporting 100 curies of curium-244 crashes, and the remaining 800 gallons of aviation fuel burns for 15 minutes. The fuel is contained in a pool with an approximate radius of 5 meters. The wind is blowing at 10 meters/second on a cloudy day. Assuming the respirable release fraction is 0.01 (1%), estimate the radiation dose commitments downwind from this accident scene.

| • | Step 1 | From HOTSI | POT Menu: Select N |
|---|---------|----------------------------------|---|
| • | Step 2 | Effective Rel | lease Height? Type 2 |
| • | Step 3 | Volume? | Type 800; press Enter |
| • | Step 4 | Release Rac | dius? Type N ; then, type 5 ; press Enter |
| • | Step 5 | Burn Time? | Type 15; push Enter |
| • | Step 6 | Ambient Ten | np? Type Y (for 20°C); press Enter |
| • | Step 7 | Nuclide? | Type cm-244; press Enter |
| • | Step 8 | Curies? | Type 100; press Enter |
| • | Step 9 | Fraction? | Type N; then type .01 |
| • | Step 10 | Conditions? | Type 2 (to indicate cloudy day). |
| • | Step 11 | Wind? | Type 10 (10 meters/second); press Enter |
| • | Result | The Plume F | Rise Summary Information Screen appears. |
| • | Step 12 | • • | e Main Outputs Options Menu to view data Enter as desired to view more data. |
| • | Step 13 | Type 1 at the the downwin | e Outputs Option Number Menu to enter d distance. |
| • | Step 14 | Type 2 to en | ter to the Output Menu. |
| • | Step 15 | Type G (grap | phics). |
| • | Step 16 | Type 3 to vie | ew Centerline 50-yr. CEDE vs. Distance graph. |
| • | Step 17 | Type 1 to se | lect COLOR. |
| | 0 | | |

The result is the graph shown on the previous page of this manual.

Step 18

Type **1** to enter the downwind plotting range.

Lesson 12 General Resuspension Code J

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 12 - General Resuspension, Code J

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, trainees will be able to model a general

resuspension of released material, using the General

Resuspension Code J of the HOTSPOT Health Physics program.

Enabling:

- At the end of this lesson, students should be able to do the following:
 - Describe the graphical output for a General Resuspension Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Resuspension output (tabular and graphical)
 - Given mock data, generate General Resuspension output (tabular and graphical)

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 12-1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives




12-#1

- At the end of this lesson, student will be able to model a general resuspension of released material, using the General Resuspension Code J Atmospheric Dispersion Model.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the graphical output for a General Resuspension Atmospheric Dispersion Model
 - Explain the assumptions involved in deriving General Resuspension output (tables and graphs)
 - Given mock data, generate General Resuspension output (tables and graphs)

Graphical Output and Assumptions—General Resuspension



12-#2

- Have the students refer to Page 12-3, General Resuspension: Graphical Output.
- Discuss the assumptions involved in this incident, as described on the Reference page.

Reference

Graphical Output and Assumptions —General Resuspension

- Page 12-3 illustrates output for a General Resuspension Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - Resuspension is modeled using the methodology contained in the "Resuspension" section of the User Manual, Appendix A.
 - Standard-person breathing rate is 1.2 cubic meters/hour.
 - A curium-244 contamination event occurs. Most of the curium is contained in an area with an effective radius of 50 meters. The average contamination level is 1,000 microcuries/square meter. Assume the resuspension factor, for the 3 meter/second prevailing wind, is 1x10⁻⁵ m⁻¹. The sun is high in a cloudless sky. Estimate the 50-year committed effective dose equivalent rates (i.e., dose commitment per hour of downwind exposure) to individuals downwind from the event.

Code Description: General Resuspension

HOTSPOT 7.01 RESUSPENSION Resuspension 4-14-94 13:03 RADIONUCLIDE: CM-244 Inhalation Class: W HALFLIFE: 18.110 years RESUSPENSION FACTOR: 1.0E-05 1/m **EFFECTIVE RADIUS:** 50 m 1.0E+03 μCi/m^2 AVG. DEPOSITION EFFECTIVE RELEASE HEIGHT: 0.00 m WIND SPEED (h=2 m): 3.0 m/s STABILITY CLASS DEPOSITION VELOCITY : 1.00 cm/s : 0.0 m INVERSION LAYER HEIGHT: NONE RECEPTOR HEIGHT SAMPLE TIME : 60.000 min MAXIMUM DOSE DISTANCE : < 0.1 km MAXIMUM CEDE :> 0.627 rem Plume Centerline $D = 0.10 \, \text{km}$ $D = 0.20 \, \text{km}$ D = 0.50 kmCHI = 1.9E-09 Ci/m^3 CHI = 9.0E-09 Ci/m^3 CHI = 2.4E-10 Ci/m^3 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: PER 1-HR EXPOSURE TIME PER 1-HR EXPOSURE TIME PER 1-HR EXPOSURE TIME SURFACE BONE 1.1E+01 rem SURFACE BONE 54.0+00 rem SURFACE BONE 1.4E+00 rem RED MARROW 8.6E+00 rem RED MARROW 5.7E-01 rem RED MARROW 1.0E-01 rem LIVER 2.6E+00 rem LIVER 1.2E+00 rem LIVER 3.1E-01 rem GONADS GONADS GONADS 1.4E-01 rem 6.3E-02 rem 1.7E-02 rem EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 6.3E-01 rem EQUIVALENT 2.9E-01 rem EQUIVALENT 7.6E-02 rem $D = 1.00 \, \text{km}$ $D = 2.00 \, \text{km}$ $D = 5.00 \, \text{km}$ CHI = 7.2E-11 Ci/m^3 CHI = 2.1E-11 Ci/m^3 CHI = 7.6E-02 Ci/m^3 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: 50-YR DOSE COMMITMENT: PER 1-HR EXPOSURE TIME PER 1-HR EXPOSURE TIME PER 1-HR EXPOSURE TIME SURFACE BONE 4.2E-01 rem SURFACE BONE 1.2E-01 rem SURFACE BONE 2.3E-02 rem 3.2E-02 rem RED MARROW RED MARROW 9.2E-03 rem RED MARROW 2.3E-02 rem LIVER 9.6E-02 rem LIVER 2.7E-02 rem LIVER 5.2E-03 rem **GONADS** 5.1E-03 rem **GONADS** 1.5E-03 rem **GONADS** 2.8E-04 rem EFFECTIVE DOSE EFFECTIVE DOSE EFFECTIVE DOSE EQUIVALENT 2.3E-02 rem **EQUIVALENT** 6.7E-03 rem **EQUIVALENT** 1.3E-03 rem

12-#3

Notes:

 Describe the code used to derive the General Resuspension Atmospheric Dispersion Model illustrated in this lesson.

Code Description: General Resuspension

• Code description — Study the table on page 12-5.

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE
NATIONAL LABORATORY


S: SETUP

| A: | Plutonium Explosion | B: | Plutonium Fire | C: Plutonium Resuspension |
|----|--------------------------|----|---------------------------------------|---------------------------|
| D: | Uranium Explosion | E | Uranium Fire | F: Nuclear Explosion |
| G: | Radiation Workplace | H: | General Plume | I: General Explosion |
| J: | General Resuspension | K: | Inhalation Dose | T: Tritium Release |
| Ŀ | HOTSPOT Library | M: | FIDLER Calibration and LUNG Screening | N: General Fire |
| | | | | Q: QUIT |


Enter Selection

12-#4

- Describe the steps involved in using HOTSPOT to model the incident involving a curium-244 contamination event.
- Inform the students that sometimes they must press Enter (or Return) in order for the computer system to accept data which they type.
- Explain that the students should use the reference for detailed information.
- Code—Explain that the students must select the specific code related to the type of incident. In this example, the students must select Code J (General Resuspension) from the HOTSPOT Main Menu.
- Nuclide—What nuclide is involved in this incident? Tell the students that this example involves the resuspension of curium-244 (cm-44).
- Deposition—Define "average deposition" for the students.



- Select General Resuspension Atmospheric Dispersion Model from the HOTSPOT Main Menu.
- **Step 1** Type **J** to select General Resuspension from the HOTSPOT Main Menu.
- Step 2 Nuclide? Type cm-244; press Enter
- Result DEP, (μCi/square meter)? Enter the average ground deposition (microcuries/square meters) and press Enter.
- Step 3 Type 1000; press Enter



12-#5

Notes:

 Release Radius—Explain that release radius is the effective radius of a circle containing 95% of the contamination (meters). In this exammple, it is 50.

• Result The Release Radius message appears:

Release Radius = ? (m) Release radius is the effective radius of a circle containing 95% of the contamination (meters).

• Step 4 Release Radius = ? (m) Type 50; press Enter

Meteorological Conditions

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

A: A stability Very unstable

B: B stability Moderately unstable

C: C stability Slightly unstable

D: D stability Neutral

E: E stability Slightly stable

F: F stability Moderately stable

G: G stability Special nighttime, low wind

Enter selection

12-#6

- Meterological Conditions—Explain that the students may enter a number (1, 2,or 3) to specify the meterological condition or a letter (A-G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.
- In this example, the number 1 indicated the correct meteorological condition (sun HIGH in sky).

- Meteorological Conditions
 - Enter a number or a letter to indicate appropriate meteorological condition.
- Step 5 Type 1 to indicate sun HIGH in sky.

Wind

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 – 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

12-#7

- Wind—Refer students to the Wind screen display.
- S = 1.0E-04? (Y/N)—Discuss the resuspension factor with the students. The default is Y, the correct choice in this example.

• WIND?

Enter the ground wind speed, in meters/second, and press ENTER (1 mph = 0.45 m/s).

• **Step 6** Type **3**

Press the **Enter** key.

• S (u = 3.0 m/s) = 1.0E-04? (Y/N)

S is the resuspension factor (1/meter). Enter "Y" to accept the above default value, or "N" if you wish to enter a new value.

• Step 7 Type Y; press Enter

Main Output Options Menu

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- T: SAMPLE TIME
- Q: Enter to Main HOTSPOT Menu.

12-#8

- Screen output—Explain that students should select 1, screen output using the default distances.
- Data Tables—The students must type1 and press Enter to view the data tables.

- Main Output Options Menu
- Screen output
- Step 8 Type 1 to view data tables.

Press Enter view more data.

Continue pressing **Enter** until you view all the data.

After you have viewed all the data, the following message appears:

"Enter the appropriate Output option number from the following menu."

Look at the Output Option Number Menu.

Output Option Number Menu

1: Enter a new Downwind Distance

2: Return to Output Menu

Q: Return to Main HOTSPOT Menu

12#9

Notes:

 Explain that students must type 2 at the Output Option Menu to return to the Main HOTSPOT Menu.

- Output Option Number Menu
- **Step 9** Type **2** at the Output Option Number Menu to return to the Output Menu.

Press Enter

Main Output Options Menu—Option G

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- T: SAMPLE TIME
- Q: Enter to Main HOTSPOT Menu.

12-#10

Notes:

 Main Output Options Menu: Option G—Explain that students need to use option G to see graphical representations of the results of the example incident's air dispersion model.

- Option G—Graphics
- **Step 10** Type **G** for Graphics.
- Result An Output option number menu appears.

- 1: CEDE Contours
- 2: Centerline CEDE as a function of Distance

TO PRINT GRAPHICS—PUSH the "P" key when the screen output is complete.

Select your printer using the SETUP option at the Main HOTSPOT MENU.

12-#11

- Output Option Number Menu.
- Student may view Centerline CEDE as a function of Distance graphical output by typing the number 2.
- Color/Monochrome—Have students type the number 1.
- Downwind Plotting Range—Have the students type 1 or 2.
- Print—If they have printer capability, the students may press P to print the graphical results (same as on Page 12-3).

- **STEP 11** Type **2** to view Centerline CEDE as a function of Distance graphical output.
- Result The following selection box appears:

1: COLOR

2: MONOCHROME / LCD

Result The following selection box appears:

DOWNWIND PLOTTING RANGE ENTER SELECTION NUMBER

1: 0.01 TO 10 km 2: 0.1 TO 100 km


Type 1

The result is a graph.

Press **P** to print the graph (if you have printer capability).

Exercise 12-1: General Resuspension

• Exercise (Pu-238)



12-#12

- Distribute Exercise for General Resuspension involving pu-238 resuspension (Appendix B contains all exercises; use these to duplicate as many copies as needed for trainees).
- Display Overhead.
- Explain that students may consult the Reference page if they wish.
- Exercise Answers: Maximum Dose Distance = <0.1 km Maximum CEDE = >1.2 rem

Reference

Exercise 12-1: General Resuspension

- Page 12-23 illustrates the graphical output for a General Resuspension Atmospheric Dispersion Model derived from the HOTSPOT Health Physics Codes program.
- The example for this exercise is based on the following assumptions:
 - There has been a plutonium-238 contamination event. Estimate the 50-year committed effective dose equivalent rates (i.e., dose commitment per hour of downwind exposure) to individuals downwind from the event. Most of the plutonium is contained in an area with an effective radius of 30 meters. The average contamination level is 150 microcuries/square meter. Assume the resuspension factor, for the 5 meter/second prevailing wind, is 5x10⁻⁵ m⁻¹. Assume D stability.

| • | Step 1 | From the HOTSPOT Main Menu, select J | | |
|---|---------|--|--|--|
| • | Step 2 | Nuclide? Type pu-238 ; press Enter | | |
| • | Step 3 | DEP? Type 150 ; press Enter | | |
| • | Step 4 | Release Radius? Type 30 ; press Enter | | |
| • | Step 5 | Condition? Type D (for D stability). | | |
| • | Step 6 | Wind? Type 5 (for 5 meters/second); press Enter | | |
| • | Step 7 | S (u = 5.0 m/s) = $2.8\text{E}-04?$ (Y/N) Type N and enter 5E-5; press Enter . | | |
| • | Step 8 | Type 1 at the Main Outputs Options Menu to view data table; press Enter as desired to view more data. | | |
| • | Step 9 | Type 1 at the Outputs Option Number Menu to enter downwind distance. | | |
| • | Step 10 | Type 2 to enter to the Output Menu. | | |
| • | Step 11 | Type G (graphics). | | |
| • | Step 12 | Type 2 to view Centerline 50-yr. CEDE vs. Distance. | | |
| • | Step 13 | Type 1 to select COLOR. | | |
| • | Step 14 | Type 1 to enter downwind plotting range. | | |

The result is the graph shown on the previous page of this manual.

Lesson 13 Radionuclides in the Workplace Code G

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 13 - Radionuclides in the Workplace, Code G

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, trainees will be able to use the Radiation

Workplace Code G of the HOTSPOT Health Physics program as a guide for initial planning of experiments and workplace

selection.

Enabling:

- At the end of this lesson, students should be able to do the following:
 - Describe the screen output for Radiation Workplace
 - Explain the assumptions involved in deriving Radiation Workplace output
 - Given mock data, generate Radiation Workplace output

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 13-1


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives



13-#1

- At the end of this lesson, students will be able to use the Radiation Workplace Code G of the HOTSPOT Health Physics Codes program as a guide for initial planning of experiments and workplace selection.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the screen output for Radiation Workplace.
 - Explain the assumptions involved in deriving Radiation Workplace output.
 - Given mock data, generate Radiation Workplace output.

Output and Assumptions—Radiation Workplace

Radionuclide: PLUTONIUM 239

Inhalation Class : W HalfLife : 2.4E+04 Years

Type of Operation is Simple Wet

Quantity of material is 5.0E+02 microcuries

Hazard Guide Value: H = 1.0+08

RECOMMENDED WORKPLACE: TYPE 2

Push "Enter" to CONTINUE

13-#2

- Have the students read the top half of page 13-3.
- Discuss the assumptions involved in this example.

Reference

Output and Assumptions —Radiation Workplace

- Page 13-3 illustrates Radiation Workplace output derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - Radiation Workplace is modeled using the methodology contained in the "Radiation Workplace" section of the User Manual.
 - An experimenter wants to pipette a solution containing a total of 500 μ Ci of class W, 239 Pu (PU-239W). The activity concentration of the solution is 20 μ Ci/g (therefore, total mass is 25g). What type of workplace should be recommended for this *simple* operation?
- Refer also to User Manual, "Radionuclides in the Workplace."

Demonstration: Radiation Workplace

HOTSPOT Health Physics Codes
VERSION 7.01
HAZARDS CONTROL DEPARTMENT
LAWRENCE LIVERMORE NATIONAL
LABORATORY

S: SETUP

| A: Plutonium Explosion | B: Plutonium Fire | C: Plutonium Resuspension |
|-------------------------|--|---------------------------|
| D: Uranium Explosion | E: Uranium Fire | F: Nuclear Explosion |
| G: Radiation Workplace | H: General Plume | I: General Explosion |
| J: General Resuspension | K: Inhalation Dose | T: Tritium Release |
| L: HOTSPOT Library | M: FIDLER Calibration and LUNG Screening | N: General Fire Q: QUIT |

Enter Selection

13-#3

- Describe the steps involved in using HOTSPOT Code G as a guide for initial planning of experiments and workplace selection.
- Explain that the students should use the Reference page for detailed information.
- Code?—Tell students to select Code G from the HOTSPOT Main Menu.
- Nuclide?—What nuclide is involved in the workplace? In this example, it is PU-239W.
- Operation—Tell students that they must enter the number of the type of operation for which they desire information.
- Quantity (μCi)?—Tell students to enter the quantity of radionuclide in microcuries.

Demonstration: Radiation Workplace

- Select Radiation Workplace from the HOTSPOT Main Menu.
- **Step 1** Type **G** to select Radiation Workplace from the HOTSPOT Main Menu.
- Result The following message appears:

The following program provides a guide for initial planning of experiments and workplace selection. It cannot be treated as a precise hazard analysis for handling radioactive materials. Further considerations may be necessary depending on the material's physical form (solid, powder, etc.), volatility, pyrophoric properties, ability to penetrate the skin, radiation dose rate, and the experience of the experimenter and the Health Physicist.

Push "Enter" to return to Menu

- Step 2 Type PU-239W.
- Result The following message appears:

Enter the Number of the appropriate operation from the following menu:

- 1: Determine Maximum Activity for TYPE 1 and TYPE 2 Workplace
- 2: Determine TYPE of Workplace Required
- Operation Enter the type of operation from the menu.
- **Step 3** Type **2**.
- Qty (μCi)? Enter the quantity of radionuclide (microcurie).
- Step 4 Type 500; press Enter.

Demonstration: Radiation Workplace

- 1: Storage
- 2: Simple Wet
- 3: Normal
- 4: Simple Dry
- 5: Complex Wet
- 6: Dry Dusty

13-#4

- Define Mass gram (the total mass of non-radioactive material involved in the operation (gram).
- Discuss a pure radionuclide.
- Discuss the six types of operations and give examples of each.

Reference

Demonstration: Radiation Workplace

Mass - gram?

Enter the total mass of the non-radioactive material involved in the operation (gram), and push Enter. Enter zero for a pure radionuclide.

• Step 5 Type 25 and press Enter.

Result The following message appears:

Enter the Number of the appropriate Type of Operation from the following menu.

- 1: Storage
- 2: Simple Wet
- 3: Normal
- 4: Simple Dry
- 5: Complex Wet
- 6: Dry Dusty

EXAMPLES

Simple Wet: Diluting stock solutions, Washing

precipitates.

Normal: No production of dry material, No

vigorous chemical reactions.

Precipitation, Filtration or centrifuging, Solvent extraction, Chromatography,

Pipetting or titrating, Ambient

temperatures.

Simple Dry: Fusion reactions, Fluorination, Transfer

of dry precipitates.

Complex Wet: Distillation, Sampling and transfer,

Evaporation of dryness, Elevated

temperatures.

Dry Dusty: Machine or hand crushing, Machining

or sawing, Sieving, Mixing.

• **Step 6** Type **2**.

Demonstration: Radiation Workplace

Enter the appropriate Output Option Number from the following menu.

- 1: SCREEN Output
- 2: PRINTER Output
- 3: Enter a new Nuclide
- 4: Describe Type 1, 2, 3
- 5: RETURN TO OUTPUT MENU
- Q: QUIT

13-#5

- Describe Output options.
- For this example, tell students to select 1, Screen Output.

Demonstration: Radiation Workplace

Output

Enter the appropriate Output Option Number from the following menu:

- 1: SCREEN Output
- 2: PRINTER Output
- 3: Enter a new Nuclide
- 4: Describe Type 1, 2, 3
- 5: RETURN TO OUTPUT MENU
- Q: QUIT
- **Step 7** Type **1**.
- Result The following results table appears:

Radionuclide: PLUTONIUM 239

Inhalation Class: W

HalfLife : 2.4E+04 Years

Type of Operation is Simple Wet

Quantity of material is 5.0E+02 microcuries

Hazard Guide Value: H = 1.0E+08

RECOMMENDED WORKPLACE: TYPE 2

Push "Enter" to CONTINUE.

- Step 8 Press Enter.
- Output The Output Options Number Menu appears.
- Step 9 Type Q.

Lesson 14 FIDLER Calibration Code M

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 14 - FIDLER Calibration, Code M

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to calibrate a

FIDLER (Field Instrument for the Detection of Low-Energy

Radiation), using the FIDLER Calibration Code M of the HOTSPOT

Health Physics program.

Enabling:

- When you complete this lesson, you should be able to do the following:
 - Describe the graphical output for FIDLER Calibration
 - Explain the assumptions involved in FIDLER Calibration
 - Given mock data, calibrate a FIDLER

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 14–1

STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives

HOTSPOT HEALTH PHYSICS CODES FIDLER CALIBRATION VERSION 7.01

Fidler Setup

| | C: CALIBRATE detector | |
|-----------|--|--|
| İ | D: DISPLAY calibration data to screen | |
| | S: SAVE calibration data to disc | |
| | R: RETRIEVE calibration data from disc | |
| Q: QUIT | | |
| , , , , , | M: Current radionuclide MIXTURE | |
| | E: EDIT calibration data | |
| | L: Detector calibration LIBRARY | |
| | P: PLUTONIUM LUNG SCREENING | |

Enter Selection

14-#1

- At the end of this lesson, students will be able to use the FIDLER
 Calibration Code M of the HOTSPOT Health Physics Codes program to
 calibrate a FIDLER (Field Instrument for the Detection of Low-Energy
 Radiation) to measure plutonium contamination on the ground. However,
 the program can be applied to any instrument suitable for measuring
 external radiation levels and non-plutonium mixtures, e.g., using a Geiger Mueller instrument for the measurement of ¹³⁷Cs ground contamination.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the screen output for FIDLER Calibration.
 - Explain the assumptions involved in deriving FIDLER Calibration output.
 - Calibrate a FIDLER.

Output and Assumptions—FIDLER Calibration

| Isotope | Halflife | (yrs) | Initial (Wt %) | @ Age | = 20.0 \ | /R (wt % |) | | |
|--|---|---|---|-------------------------------|---|------------------|------------------|---|--------|
| PU-238 PU-239 PU-240 PU-241 PU-242 AM-241 | 87. 24065. 6537. 14. 376300. 432. | 35 | 0.0400 93.3400 6.0000 0.5800 0.0400 0.0000 | | 0.034 93.286 5.987 0.220 0.040 0.352 | 2 3 7 0 | Check 5.900 µ | ium-241 Source I ICi 17) = 1.0 | Data |
| | Source-To-Detector Height = 30 cm Sample Time = 1.00 min ALPHA Curie: 9.0E-02 curies/gram | | | | | | | | |
| 1 microcu | 1 microcurie of Am-241 = 7.4E+00 alpha microcurie of Mix ***The following data are for μCi of MIX*** | | | | | | | | |
| WINDOW (keV) | EFFICIENCY cpm μg/m ² | (SA) cpm μ <u>Ci/m</u> ² | DETECTION Area <u>μCi/m</u> ² | LIMITS Point <u>μCi</u> | BKDG <u>cpm</u> | SOURCI | E | K <u>m</u> 2 | SDEV |
| 17 60 | 2.0E+01 3.8E+01 | | 4.5E-01 3.1E-01 | 1.5E-01 1.6E-01 | | 15048 36835 | | 0.34 0.51 | 7 4 |

Eberline 33425 66776 7-14-93 10:21

14-#2

- Have the students read the top half of page 14-3.
- Discuss the assumptions involved in this example.

Reference

Output and Assumptions —FIDLER Calibration

- Page 14-3 illustrates FIDLER Calibration output derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - FIDLER Calibration is modeled using the methodology contained in the "FIDLER Calibration" section of the User Manual.
 - The FIDLER Calibration Code M of the HOTSPOT Health Physics Codes program calibrates a FIDLER to measure plutonium contamination on the ground.
 - Read "Calibration of the FIDLER Detector" and "Determination of the Areal Counting Efficiency" in the FIDLER Calibration section of the User Manual.

HOTSPOT Health Physics Codes VERSION 7.01 HAZARDS CONTROL DEPARTMENT LAWRENCE LIVERMORE NATIONAL LABORATORY

S: SETUP

A: Plutonium Explosion B: Plutonium Fire C: Plutonium

Resuspension

D: Uranium Explosion E: Uranium Fire F: Nuclear Explosion

G: Radiation Workplace H: General Plume I: General Explosion

J: General K: Inhalation Dose T: Tritium Release

Resuspension

L: HOTSPOT Library M: FIDLER Calibration N: General Fire

and LUNG Screening

Q: QUIT

Enter Selection

14-#3

- Describe the steps involved in using FIDLER Calibration Code M as a guide for initial planning of experiments and workplace selection.
- Explain that the students should use the Reference page for detailed information.
- Code?—Tell students to select Code M from the HOTSPOT Main Menu.
- FIDLER Main Menu—Tell students the goal of this procedure.
- Procedure—Outline the steps in this procedure.

- **Step 1** To select FIDLER Calibration from the HOTSPOT Main Menu, Type **M**.
- Result The following message may appear:

Your current RAM is not large enough to run the FIDLER program from the HOTSPOT menu. EXIT HOTSPOT and run the program named FIDLER.

If this message appears, quit the HOTSPOT program and open FIDLER at the DOS c:> prompt.

- Step 2 Type FIDLER at the DOS prompt.
- Result The FIDLER Main Menu appears.
- Procedure? This procedure describes the six-point method of calibrating a FIDLER instrument with a single ²⁴¹Am check source. Calibrating the FIDLER to measure ²³⁸Pu check source demonstrates a radionuclide-specific calibration. The primary goal of the calibration procedure is to determine the instrument's counting efficiency for an assumed uniformarea contamination per square meter of surface. This parameter is referred to as the areal counting efficiency (Sa). Additionally, the Limit of Sensitivity (LOS) for both a distributed area source and a single point source are determined.

241 AM Check Source Calibration procedure follows:

- Operation? From the FIDLER Main Menu, enter the letter which represents the type of operation.
- **Step 3** Type **R** to select RETRIEVE calibration from disc.
- Result Do you wish to browse the detector library first? (Y/N)

FILE # 1 : LUNG-Roxanne Luna FIDLER + PS-1 RASCAL 2344
FILE # 2 : LUNG-Robert Wills FIDLER + PS-1 RASCAL 2344
FILE # 3 : LUNG-Kevin Anderson FIDLER + PS-1 RASCAL 2344

FILE # 4 : Eberline 33425 66776 333 55555

FILE # 5 : Custom Inc. 324 445 7777777 999999999

Push "Enter" to return to menu

14-#4

- Describe the list of calibration files
- Define "file number."
- Tell students to type the number 4 and to press Enter.

- Step 4 Type Y; press Enter.
- Result Entering Y allows you to review the current list of calibration files contained on your FIDLER disc. The first file contains a standard weapons-grade plutonium mixture.
- Step 5 Press Enter to be prompted for a file number.
- Result The following message appears:

Enter the Detector file; Position Number (e.g., 1, 2, ...), and Push "Enter."

- **Step 6** Type **4**; press **Enter**.
- Result The displayed calibration chart, for calibration file number 4, contains the desired plutonium mixture.

Note: Thisis a file from a previous FIDLER calibration session that has been stored in the FIDLER Library.

| Isotope | Halflife | (yrs) | Initial (Wt %) | @Age | = 20.0 \ | /R (wt % |) | | |
|--|--|---|---|-------------------------------|---|------------------|------------------|---|--------|
| PU-238 PU-239 PU-240 PU-241 PU-242 AM-241 | 87. 24065. 6537. 14.3 376300. 432. | 35 | 0.0400 93.3400 6.0000 0.5800 0.0400 0.0000 | | 0.033 93.286 5.986 0.210 0.040 0.362 | 2 7 3 0 | Check 5.900 µ | ium-241 Source tCi 17) = 1.0 | Data |
| ALPHA C | Source-To-Detector Height = 30 cm Sample Time = 1.00 min ALPHA Curie: 9.0E-02 curies/gram 1 microcurie of Am-241 = 7.23E+00 alpha microcurie of Mix | | | | | | | | |
| | | ***Th | ne following dat | a are for | μCi of N | ЛIX*** | | | |
| WINDOW (keV) | EFFICIENCY cpm μg/m ² | (SA) cpm μ <u>Ci/m</u> ² | DETECTION Area <u>μCi/m²</u> | LIMITS Point <u>μCi</u> | BKDG <u>cpm</u> | SOURCI | E | K <u>m</u> 2 | SDEV |
| 17 60 | 5.1E+01 3.9E+01 | | 1.8E-01 3.0E-01 | 9.0E-02 1.5E-01 | | 15048 36835 | | 0.50 0.51 | 7 4 |

Eberline 33425 66776 333

55555


14-#5

- Describe the displayed calibration chart, for calibration file number 1.
- Explain the procedure for calibrating a new instrument.

- Step 7 Press Enter to return to the FIDLER Main Menu.
- Result The FIDLER Main Menu appears. Now, calibrate a new FIDLER instrument.
- Step 8 Type C.
- Result The following message appears:

START OVER WITH NEW MIXTURE? (Y/N)

- Step 9 Type N to use the currently retrieved mixture.
- Result Again, the current calibration data appear for confirmation of the mixture.
- Step 10 Press Enter.
- Result An illustration and a selection NUMBER menu appear:



Enter a selection NUMBER

1: K factor known (or accept a default value)
2: Determine Sa, and K Factor (Full calibration)

Q: NO! Leave Calibration alone and RETURN to main menu

14-#6

Notes:

• Explain how to determine Sa, and K Factor (Full calibration).

- **Step 11** Type **2** to use the full six-point method.
- Result SCALER ? (Y/N)

If you are using a scaler with the detector, enter "Y". If you are using a rate meter, enter "N".

- **Step 12** Type **Y** if you are using a scaler (e.g., Eberline ESP-2); otherwise, enter "N" [therefore, a rate meter (e.g., PRM-5) is assumed].
- Result You will be prompted for the SAMPLE TIME.
- **Step 13** Type **1** (for one minute); press **Enter**, etc., as required.
- Result You will be prompted for the Detector ID information (e.g., Barcode numbers, Survey meter E-243, Detector 35A, calibration date, etc. All of these fields are optional.
- Step 14 Type E-243 35A; press Enter.
- Result You will be prompted for the Detector Height, h (cm). Note: h is the Source-to-detector distance, cm.
- **Step 15** Type **30** to enter the distance separating the face of detector and the check source, and push **Enter**.
- Result The following menu appears:

Select Calibration Option

- 1: 60 keV region
- 2: 17 keV region
- 3: Both 60 keV and 17 keV regions
- **Step 16** Type **3**.
- Result Source (μCi)?

Enter the activity of the calibration source used (microcuries).

| Isotope | Halflife | (yrs) | Initial (Wt %) | @Age | = 20.0 \ | ′R (wt % |) | | |
|--|---|---|---|-------------------------------|---|------------------|------------------|---|------|
| PU-238 PU-239 PU-240 PU-241 PU-242 AM-241 | 87.7 24065. 6537. 14.3 376300. 432.3 | 35 | 0.0400 93.3400 6.0000 0.5800 0.0400 0.0000 | | 0.034 93.286 5.987 0.220 0.040 0.352 | 2 3 7 0 | Check 5.900 μ | ium-241 Source [.Ci 17) = 1.(| |
| ALPHA C | Source-To-Detector Height = 30 cm Sample Time = 1.00 min ALPHA Curie: 9.0E-02 curies/gram 1 microcurie of Am-241 = 7.4E+00 alpha microcurie of Mix | | | | | | | | |
| | | ***Th | ne following data | a are for | μCi of N | /IIX*** | | | |
| WINDOW (keV) | EFFICIENCY cpm μg/m ² | (SA) cpm μ <u>Ci/m</u> ² | DETECTION Area μCi/m ² | LIMITS Point <u>µCi</u> | BKDG <u>cpm</u> | SOURCI | Ξ | К <u>m²</u> | SDEV |
| 17 60 | 2.0E+01 3.8E+01 | | 4.5E-01 3.1E-01 | 1.5E-01 1.6E-01 | | 15048 36835 | | 0.34 0.51 | 7 |

Eberline 33425 66776 7-14-93 10:21

14-#7

Notes:

• Explain how to enter 17-keV and 60-keV window data.

• **Step 17** Type **5.9**; press **Enter**.

Result Self (17)

The Self (17) prompt appears. Enter the 17-keV window self attenuation factor for the americium-241 check source. (Enter a fractional value between 0.001 and 1.)

- Step 18 Type 1.0; press Enter.
- Result BKGD (17-keV)?

Enter the 17-keV window background count rate

(counts/minute).

- Step 19 Type 450; press Enter.
- Result Is Count Rate Input Correct? (Y/N)
- **Step 20** Type **Y**. If the count rate is not correct, type N and you will recycle through the background input sequence.
- Result
 Next, you will be prompted for 60-keV window data. The next series of prompts will sequentially ask you for the 17-keV

and 60-keV window count rates at the six radial positions, 0, 20, 40, 60, 80, and 100 cm. Input the values shown on the

following table:

Eberline 33425 66776 333 55555

Detector Manufacturer : Harshaw Detector Model : 35 Detector S/N : 66776

Meter Manufacturer : Eberlin Meter Model : ESP2 Meter S/N : 33425

Check Source I.D. : 22132 Calibration Date : 7-16-93 Calibrated By : SGH

Source-To- Detector Height = 30 centimeters Sample-Time = 1.00 min

Plutonium Mixture : Am-241 Check Source : 5.900 microcuries Self (17) = 0.6000

17-keV Window Background : 450 Counts per minute. 60-keV Window Background : 750 Counts per minute.

| Radial | 17-keV Window | 60-keV Window |
|-------------|---------------|---------------|
| Posiiton | TOTAL | TOATAL |
| <u>(cm)</u> | <u>(cpm)</u> | <u>(cpm)</u> |
| 0 | 15048 | 336835 |
| 20 | 8602 | 23118 |
| 40 | 3148 | 9806 |
| 60 | 1318 | 4614 |
| 80 | 766 | 2584 |
| 100 | 582 | 1684 |

Upon confirming the final input (100-cm distance), the final calibration data appears on the computer monitor.

Lesson 15 LUNG Screening Code M

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 15 - LUNG Screening, Code M

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to screen for

plutonium uptake in the lung, using a FIDLER (Field Instrument for the Detection of Low-Energy Radiation) detector and the LUNG Screening Code M of the HOTSPOT Health Physics program.

Enabling:

- When you complete this lesson, you should be able to do the following:
 - Explain the assumptions involved in LUNG Screening
 - Given mock data, screen people for possible plutonium deposition in the lung

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC) Exercise Number 15–1

STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives

FIDLER

PLUTONIUM LUNG SCREENING

F: Fidler Setup

C: CALIBRATE FIDLER for lung screening

D: DISPLAY lung screen results

S: SAVE lung screening session

R: RETRIEVE lung screening session from disc

Q: QUIT

M: Current radionuclide MIXTURE data

E: EDIT Lung Screening data

L: LUNG COUNT

Enter Selection

15-#1

- At the end of this lesson, students will be able to use the FIDLER LUNG Screening Code M of the HOTSPOT Health Physics Codes program to screen for plutonium uptake in the lung using a FIDLER detector.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the screen output for LUNG Screening.
 - Explain the assumptions involved in deriving LUNG Screening output.
 - Perform LUNG Screening using a FIDLER.

Output and Assumptions—LUNG Screening

| <u>Isotope</u> | Halflife (yrs) | Initial (Wt %) | @Age = 20.0 | YR (wt %) | |
|------------------|--|------------------|----------------|------------|---------------|
| PU-238 | 87.74 | 0.0400 | 0.033 | 39 Ameri | cium-241 |
| PU-239 | 24065. | 93.3400 | 93.283 | 6 Check | k Source Data |
| PU-240 | 6537. | 6.0000 | 5.986 | 5.900 | μCi |
| PU-241 | 14.35 | 0.5800 | 0.210 |)3 | |
| PU-242 | 376300. | 0.0400 | 0.040 | 00 | |
| AM-241 | 432.2 | 0.0000 | 0.362 | 25 | |
| Height: 5 ft 8 i | 8.99E-02 curie n Weight CIENCY: 3.3E+0 | :: 120 lbs | Chest Wall: 1. | 5 cm | |
| MDA: AM-24 | 41 = 7.3 nCi | Mix = 53nCi | | | |
| | | CHEC | | | |
| | | ROUND SOUR | | | |
| TIME (min): | 5.0 | | - | | |
| COUNTS: | 3750 | 36835 | | 750 | |
| RATE (cpm): | 750 | 36835 | 900 | 150 | |
| | | | LUNG | SCREEN | RESULTS |
| | | | AM-24 | 1 MIX | SDEV |
| | | | (nCi) | (nCi) | (%) |
| | Desposited in Lui | | 45 | 328 | 12 |
| 50-year comm | itted Effective Do | se Equivalent (ı | mix): | 44.4E+02 r | em |

LUNG SCREEN: Roxanne Luna FIDLER + PS-1 RASCAL 2344 15-#2

- Have the students read the top half of page 15-3.
- Discuss the assumptions involved in this example.

Reference

Output and Assumptions —LUNG Screening

- Page 15-3 (Figure 15-#2) illustrates LUNG Screening output derived from the HOTSPOT Health Physics Codes program.
- This example is based on the following assumptions:
 - LUNG Screening is modeled using the methodology contained in the "LUNG Screening" section of the User Manual.
 - The LUNG Screening Code M of the HOTSPOT Health Physics Codes program screens for plutonium uptake in the lung using a FIDLER detector.
 - Read the LUNG Screening section of the User Manual.

Demonstration: LUNG Screening

HOTSPOT Health Physics Codes VERSION 7.01 HAZARDS CONTROL DEPARTMENT LAWRENCE LIVERMORE NATIONAL LABORATORY

S: SETUP

A: Plutonium Explosion B: Plutonium Fire C: Plutonium

Resuspension

D: Uranium Explosion E: Uranium Fire F: Nuclear Explosion

G: Radiation Workplace H: General Plume I: General Explosion

J: General K: Inhalation Dose T: Tritium Release

Resuspension

L: HOTSPOT Library M: FIDLER Calibration N: General Fire

and LUNG Screening

Q: QUIT

Enter Selection

15-#3

- Describe the steps involved in using FIDLER Calibration Code M to screen for plutonium uptake in the lung using a FIDLER detector.
- Explain that the students should use the Reference page for detailed information.
- Code?—Tell students to select Code M from the HOTSPOT Main Menu.
- FIDLER Main Menu—Tell students the goal of this procedure.
- Procedure—Outline the steps in this procedure.

Reference

Demonstration: LUNG Screening

- **Step 1** Type **M** to select LUNG Screening from the HOTSPOT Main Menu.
- Result The following message may appear:

Your current RAM is not large enough to run the FIDLER program from the HOTSPOT menu.

EXIT HOTSPOT and run the program named FIDLER.

If this message appears, quit the HOTSPOT program and open FIDLER at the DOS c:> prompt.

- Step 2 Type FIDLER at the DOS prompt.
- Result The FIDLER Main Menu appears.

HOTSPOT HEALTH PHYSICS CODES FIDLER CALIBRATION VERSION 7.01

Fidler Setup

| | C: CALIBRATE detector |
|---------|--|
| | D: DISPLAY calibration data to screen |
| | S: SAVE calibration data to disc |
| | R: RETRIEVE calibration data from disc |
| Q: QUIT | |
| | M: Current radionuclide MIXTURE |
| | E: EDIT calibration data |
| | L: Detector calibration LIBRARY |
| | P: PLUTONIUM LUNG SCREENING |
| | |

Enter Selection

- Procedure? This procedure screens for plutonium uptake in the lung using a FIDLER detector.
- Operation? From the FIDLER Main Menu, enter the letter which represents the type of operation.

| Isotope | Halflife (yrs) | Initial (Wt %) | @ Age = 15.0 YR (wt %) | |
|---------|----------------|----------------|------------------------|--|
| PU-238 | 87.74 | 0.0400 | 0.0355 | |
| PU-239 | 24065. | 93.3400 | 93.2997 | |
| PU-240 | 6537. | 6.0000 | 5.9905 | |
| PU-241 | 14.35 | 0.5800 | 0.2810 | |
| PU-242 | 376300. | 0.0400 | 0.0400 | |
| AM-241 | 432.2 | 0.0000 | 0.2950 | |
| | | | | |

SPECIFIC ACTIVITY

ALPHA Curie: 0.0879 curies/gram TOTAL Curie: 0.3773 curies/gram

1 alpha microcurie of Mix = 0.1151 microcurie of Am-241

-OR-

1 microcurie of AM-241 = 8.6883 alpha microcurie of Mix

(Figure 15-14a)

| Isotope | Halflife (yrs) | Initial (Wt %) | @ Age = 21.0 YR (wt %) | |
|---------|----------------|----------------|------------------------|--|
| PU-238 | 87.74 | 0.0400 | 0.0339 | |
| PU-239 | 24065. | 93.3400 | 93.9867 | |
| PU-240 | 6537. | 6.0000 | 5.9905 | |
| PU-241 | 14.35 | 0.5800 | 0.2810 | |
| PU-242 | 376300. | 0.0400 | 0.0400 | |
| AM-241 | 432.2 | 0.0000 | 0.2950 | |
| AM-241 | | | | |

SPECIFIC ACTIVITY

ALPHA Curie: 0.0879 curies/gram TOTAL Curie: 0.3773 curies/gram

-OR-

(Figure 15-14b)

15-#4a & 4b

- Explain the tables on this page.
- Tell students to type P to select PLutonium Lung Screening from the FIDLER Main Menu; type C; press Enter, type N; press Enter; type 21.


¹ alpha microcurie of Mix = 0.1151 microcurie of Am-241

¹ microcurie of AM-241 = 8.6883 alpha microcurie of Mix

- **Step 3** Type **P** to select Plutonium Lung Screening from the FIDLER Main Menu.
- Result The Plutonium Lung Screening Main Menu appears (see page 15–1).
- **Step 4** Type **C** to Calibrate FIDLER for lung screening; press **Enter**.
- Result
 MIX KNOWN? (Y/N)
 If you know the mix data, enter "Y". If you do not know the mix data, enter "N".
- Step 5 Type N.
- Result The default MIX table appears (illustrated in Figure 15-#4a).
- Step 6 Press Enter.
- Result MIX AGE?

The MIX AGE? YR prompt requests you to enter the time (years) that has elapsed since your mix data were measured or calculated. Default is 15 Yr.

- Step 7 Type 21; press Enter.
- Result The MIX table appears (see Figure 15-#4b).



15#5

- Describe the drawing representing the FIDLER Lung Screen Calibration Setup.
- Explain the procedure for calibrating the FIDLER.
- Define "counting time."


- **Step 8** After viewing the MIX table (15-#4b), press **Enter.**
- Result Source (μCi)?

The FIDLER LUNG SCREENING CALIBRATION SETUP screen appears. Enter the activity of the Am-241 calibration

- source used (microcuries), and push Enter.
- Step 9 Type 5.9; press Enter; type Y.
- Result COUNTING TIME (minutes)?

The system requests you to enter the counting time for the

check source calibration.



Notes:

• Explain positioning of the FIDLER as shown in the illustration on this page.

- Step 10 Type 1; press Enter; type Y.
- Result COUNTS?

The system requests you to enter the total counts collected with the americium-241 check source positioned directly under the detector at a source-to-detector height of 30 cm.

- Step 11 Type 36835; press Enter; type Y.
- Result BKGD-TIME?

Enter the background counting time (minutes), and push

Enter.

- Step 12 Type 5; press Enter; type Y.
- Result BKDG (LUNG) Counts?

Enter the background (Counts).

- Step 13 Type 3750; press Enter; type Y.
- Result This is the end of the <u>calibration</u> sequence.

Demonstration: LUNG Screening—Lung Count

| <u>Isotope</u> | Halflife (yrs) | Initial (Wt %) | @Age = 20.0 Y | 'R (wt %) | |
|---|---------------------|----------------------|---------------|-------------|----------------|
| PU-238 | 87.74 | 0.0400 | 0.0339 | 9 Americ | ium-241 |
| PU-239 | 24065. | 93.3400 | 93.2836 | 6 Check | Source Data |
| PU-240 | 6537. | 6.0000 | 5.9867 | 7 5.900 լ | ιCi |
| PU-241 | 14.35 | 0.5800 | 0.2103 | • | |
| PU-242 | 376300. | 0.0400 | 0.0400 | 0 | |
| AM-241 | 432.2 | 0.0000 | 0.362 | 5 | |
| ALPHA Curie: $8.99E-02$ curies/gram 1 μ Ci of Am-241 = $7.23E+00$ alpha μ Ci-mix Height: 5 ft 8 in Weight: 120 lbs Chest Wall: 1.5 cm FIDLER EFFICIENCY: $3.3E+03$ CPM/ μ Ci of AM-241 in lung SDEV: 0.53% | | | | | |
| MDA: AM-2 | 41 = 7.3 nCi | | ODOO | NET | |
| | BACKG | CHECK ROUND SOURC | | | |
| TIME (min): | 5.0 | | | | |
| COUNTS: | 3750 | | | 750 | |
| RATE (cpm): | 750 | 36835 | 900 | 150 | |
| | | | LUNG | SCREEN | RESULTS |
| | | | AM-241 | | SDEV |
| | | | (nCi) | | (%) |
| Alpha Activity | Desposited in Lu | na · | 45 | 328 | 12 |
| | nitted Effective Do | | | 44.4E+02 re | · - |

LUNG SCREEN: E-243 35A

15-#7

Notes:

• Explain the procedure for performing a Lung Count.

Demonstration: LUNG Screening—Lung Count

Select LUNG COUNT from the FIDLER Plutonium Lung Screening Main Menu.

- Step 1 Type L to select LUNG COUNT.
- Result Detector ID information?

The system requests Detector ID information (for example, Survey meter E-243, Detector 35A). Any combination of letters or numbers (maximum 60 characters) may be input.

- Step 2 Type E-243 35A; press Enter.
- Result HEIGHT (Feet.inches)?

Enter the height of the person in feet and inches using the following format: f(x) = f(x) where f(x) = f(x) is inches.

- Step 3 Type 5.08; press Enter; type Y.
- Result WEIGHT (pounds)?
 Enter the weight of the person (pounds).
- Step 4 Type 120; press Enter; type Y.
- Result SAMPLE-TIME (minutes)
 Enter the counting time (minutes) for the lung scan.
- Step 5 Type 5; press Enter; type Y.
- Result SAMPLE COUNTS?

Enter the total counts acquired during the lung scan. NOTE: FIDLER should be placed over the RIGHT LUNG between THE STERNUM and CLAVICLE (Collarbone). The sternum is the long flat chest bone joining the 2 sets of ribs. See Figure 15-#6.

- Step 6 Type 4500; press Enter; type Y.
- Result The LUNG SCREEN RESULTS table appears. Pressing Enter returns you to the FIDLER Plutonium Lung Screening Menu.

Lesson 16 Output Options C, M, Z, D, O, I, and T

LESSON PLAN HOTSPOT HEALTH PHYSICS CODES

LESSON 16 – Output Options C, M, Z, D, O, I, and T

TIME:

30 minutes

LESSON LEARNING OBJECTIVES

Terminal: At the end of this lesson, students will be able to describe the

Options C, M, Z, D, O, I, and T of the HOTSPOT Health Physics

program.

Enabling:

- At the end of this lesson, students should be able to:
 - Describe the Options C, M, Z, D, O, I, and T used in developing Atmospheric Dispersion Models derived from the HOTSPOT Health Physics Codes program.
 - Given mock data, modify Atmospheric Dispersion Model output (tables and graphs), using the HOTSPOT Health Physics Codes program and Options C, M, Z, D, O, I, and T.

INSTRUCTIONAL APPROACH

The mode of delivery for this lesson is lecture, using several job aids and reference materials to provide students with an overview of the HOTSPOT Health Physics Codes application.

EQUIPMENT AND INSTRUCTIONAL AIDS

Overhead projector IBM PC, XT, AT, or compatible HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)


STUDENT MATERIALS

Student Manual

REFERENCES

HOTSPOT User's Manual (HOTSPOT Health Physics Codes for the PC)

Lesson Objectives



16-#1

Notes:

- At the end of this lesson, students will be able to describe the Output Options C, M, Z, D, O, and I and use them in developing Atmospheric Dispersion Models using the HOTSPOT Health Physics Codes program.
- Explain the Lesson Objectives.

Lesson Objectives

- At the end of this lesson, students should be able to:
 - Describe the Options C, M, Z, D, O, and I, used in developing Atmospheric Dispersion Models derived from the HOTSPOT Health Physics Codes program.
 - Given mock data, modify Atmospheric Dispersion Model output (tables and graphs), using the HOTSPOT Health Physics Codes program and Options C, M, Z, D, O, and I.

Options Demonstration—Option C

• Main Output Options Menu—Option C

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Return to Main HOTSPOT Menu.

16-#2

Notes:

- Briefly describe Options C, M, Z, D, O, and I (used to change variables which influence the results and graphical output).
- Explain the use of Option C (Default Contour Settings).

Options Demonstration—Option C

- Options C, M, Z, D, O, and I (These options allow you to change variables to influence the results and graphical output).
- · Option C
- Step 1 Type C to change DEFAULT CONTOUR SETTINGS.
- Result The following menu appears:
 - 1: Change Default CEDE Contours values.
 - 2: Change Default DEPOSITION Contour values.

NOTE: To permanently change the default settings, use the SETUP procedure.

- Q: Return to MAIN OUTPUT OPTION MENU.
- Step 2 Type 1 (to change default CEDE Contours values).
- Result The following menu appears:

Enter a new CEDE Target value, rem, and push Enter.

HOTSPOT will bracket this value by a factor of 10.

EXAMPLE Target = 2 rem : 20 rem - 2 rem - 0.2 rem

- **Step 3** Type **4** (to enter a new CEDE Target value).
- Step 4 Press Enter
- Result The CEDE Target value has been changed.

Options Demonstration—Option M

Main Output Options Menu—Option M

Main Output Options Menu

| 1: | SCREEN | Output | Default | Distances |
|----|-----------|--------|-----------|-----------|
| 2: | SCREEN | Output | You Enter | Distances |
| 3: | PRINTER | Output | Default | Distances |
| 4: | PRINTER | Output | You Enter | Distances |
| 5: | DISK FILE | Output | Default | Distances |
| 6: | DISK FILE | Output | You Enter | Distances |

- G: GRAPHICS
- C: Change DEFAULT CONTOUR SETTINGS
- M: Change METEOROLOGICAL PARAMETERS and Release Height
- Z: Change RECEPTOR HEIGHT (z)
- D: Change DEPOSITION VELOCITY
- O: Enable prompt for OFF AXIS Positions
- I: INVERSION HEIGHT (Mixing Layer)
- Q: Return to Main HOTSPOT Menu.

16#3

Notes:

- Meteorological Conditions—Explain that the students may enter a number (1, 2, or 3) to specify the meteorological condition (sun high in sky; sun low in sky or cloudy; night) or a letter (A–G) to specify a stability class.
- Refer students to the Meteorological Conditions screen display.

Options Demonstration—Option M

- Option M
- **Step 1** Type **M** to change METEOROLOGICAL PARAMETERS.
- Result The following menu appears:

Choose appropriate meteorological conditions from the following menu—Enter a NUMBER or LETTER.

- 1. Sun HIGH in the sky
- 2. Sun LOW in the sky or cloudy
- 3. NIGHT

Or, if you prefer to enter a specific stability classification,

- A: A stability Very unstable
- B: B stability Moderately unstable
- C: C stability Slightly unstable
- D: D stability Neutral
- E: E stability Slightly stable
- F: F stability Moderately stable
- G: G stability Special nighttime, low wind

Enter selection

- **Step 2** Type **1**, **2**, **or 3** (to indicate meteorological conditions).
- Result The WIND menu appears:

Options Demonstration—Wind

• Wind Menu for Option M

| NAME OF WIND | OBSERVABLE FEATURES | MPH | M/S |
|-------------------|-------------------------------------|---------|---------|
| calm | Smoke rises vertically | < 1 | < 0.5 |
| light Atmospheric | Smoke drifts downward | 1 – 3 | 0.5 – 1 |
| light breeze | Wind felt on face; leaves rustle | 3 - 7 | 1 – 3 |
| gentle breeze | Leaves and twigs in constant motion | 7 – 12 | 3 – 5 |
| moderate breeze | Raises dust and loose paper | 12 – 18 | 5 – 8 |
| fresh breeze | Small tress begin to sway | 18 – 24 | 8 – 11 |
| strong breeze | Large branches in motion | 24 - 31 | 11 – 14 |
| moderate gale | Whole trees in motion | 31 – 38 | 14 – 17 |
| fresh gale | Twigs break off; walking impeded | 38 - 46 | 17 – 21 |
| strong gale | Slight structural damage occurs | 46 – 54 | 21 – 24 |
| whole gale | Tree uprooted; structural damage | 54 – 63 | 24 – 28 |
| storm | Very rare, widespread destruction | 63 – 75 | 28 – 34 |
| hurricane | | > 75 | > 34 |

16-#4

Notes:

• Wind — Refer students to the Wind screen display.

Options Demonstration—Wind

- Option M
- WIND?
- Step 1 Type a number (meters/second) to specify wind conditions.
- Step 2 Press Enter
- Result The meteorological conditions used in the model have been changed.

Options Demonstration—Option Z

Option Z—Change Receptor Height

Enter the receptor height, meters, and push "Enter."

LIMITS: [0 - 500 meters]

NOTE: The receptor height is the distance above ground level at which the concentration is calculated. The default height is ground level (z = 0).

16-#5

Notes:

 Define "receptor height"; discuss Option Z; have students refer to the receptor height screen display message.


Options Demonstration—Option Z

- Option Z
- Receptor Height
- **Step 1** Type a number (**0-500**).
- Step 2 Press Enter
- Result A message appears to indicate that the system is changing the value.

| Working | one moment | please |
|---------|------------|--------|
|---------|------------|--------|

Options Demonstration—Option D

Option D—Change Deposition Velocity



17-#6

Notes:

• Define 'deposition velocity" and discuss why one would change it.

Options Demonstration—Option D

- Option D
- Deposition Velocity
- Step 1 Type D (to change the deposition velocity).
- Result The following message appears:

HOTSPOT is currently using a deposition velocity of 0.000 centimeters per second. Do you want to change this value?

• Step 2 Type Y

Enter the new deposition velocity, in centimeters per second, and push "Enter".

Allowable Range (0 to 10 cm/sec)


- **Step 3** Type **7**
- Step 4 Press Enter
- Result The following message flashes on the screen:

Workingone moment please.

Then, the system returns to the Main Output Options Menu.

Options Demonstration—Option O

 Option O—Enable prompt for OFF AXIS Positions



16#7

Notes:

• Explain changing off-axis positions (Option O).

Options Demonstration—Option O

- Option O
- OFF AXIS Positions
- **Step 1** Type **O** (to enable prompts for OFF AXIS Positions).
- Result The following message appears:

Do you wish prompts for off-axis distance? (Y/N)

- Step 2 Type Y
- Result The next time you choose to view results tables or graphical output, the system will display the prompts for off-axis distance.

Options Demonstration—Option I

Option I—Inversion Height (Mixing Layer)



16#8

Notes:

 Define "inversion height" and explain the conditions under which one would want to change it (Option I).

Options Demonstration—Option I

- Option I
- Inversion Height
- **Step 1** Type **I** (to enter a new inversion height).
- Result The following message appears:

Do you want to enter an Inversion Height? (Y/N)

Default = N (No Inversion, assumes no trapping layer)

- Step 2
 Type Y
- Result The following message appears:

Enter the new Inversion Height, meters, and push "Enter."

NOTE: The inversion height must exceed the effective release height and the receptor height by a minimum of 10 meters.

- **Step 3** Type **500**
- Step 4 Press Enter


Appendix A HOTSPOT Health Physics Codes User Manual

Appendix A: Gaussian Model Algorithms

There are many implementations of the Gaussian model, and so for completeness, the following summary is included. The Gaussian model has been widely used and verified in the scientific community and is still the basic workhorse for initial atmospheric dispersion calculations. The Gaussian model generally produces results that agree well with experimental data, and as a result, has found its way into most governmental guidebooks, and is also used and accepted by the Environmental Protection Agency (EPA, 1978). The origin of the Gaussian model is found in work by Sutton (1932), Pasquill (1961, 1974), and Gifford (1961, 1968). Additional background and supplemental information on the Gaussian model can be found in Turner (1969), Hanna, et al. (1982, 1987, 1989).

Coordinate System

In the HOTSPOT codes, the coordinate origin is located at ground level, beneath the point of radionuclide release (x = 0, y = 0, z = 0). The x axis is the DOWN-WIND axis, extending horizontally with the ground in the average wind direction. The y axis is the CROSSWIND axis, perpendicular to the downwind axis, also extending horizontally. The z axis extends vertically. A plume travels along, or parallel to, the DOWNWIND axis.



HOTSPOT coordinate system

18-S/1207-B-1

Gaussian Equation

The following Gaussian model equations determine the atmospheric concentration of a gas or an aerosol:

$$C(x, y, z, H) = \frac{Q}{2\pi\sigma_{y}\sigma_{z}u} \exp\left[-\frac{1}{2}\left(\frac{y}{\sigma_{y}}\right)^{2}\right] \left\{\exp\left[-\frac{1}{2}\left(\frac{z-H}{\sigma_{z}}\right)^{2}\right] + \exp\left[-\frac{1}{2}\left(\frac{z+H}{\sigma_{z}}\right)^{2}\right]\right\} \exp\left[-\frac{\lambda x}{u}\right] .$$
(Eq. B-1)

If the inversion layer option is in effect, and σ_z exceeds the inversion height (*L*), the following equation is used.

$$\sigma_{z} > L:$$

$$C(x, y, z, H) = \frac{Q}{\sqrt{2\pi}\sigma_{y}Lu} \exp\left[-\frac{1}{2}\left(\frac{y}{\sigma_{y}}\right)^{2}\right] \exp\left[-\frac{\lambda x}{u}\right] . \tag{Eq. B-2}$$

To avoid the sharp transition between the two above equations, the transition into the inversion layer equation begins when σ_z equals 70% of L, and is complete when σ_z equals L. Between these two values, the two equations are linearly interpolated.

where—

C = Time-integrated atmospheric concentration (Ci-sec)/(m³).

Q = Source term (Ci).

H = Effective release height (m).

 λ = Radioactive decay constant (s⁻¹).

x = Downwind distance (m).

y =Crosswind distance (m).

z = Vertical axis distance (m).

 σ_y = Standard deviation of the integrated concentration distribution in the crosswind direction (m).

 σ_Z = Standard deviation of the integrated concentration distribution in the vertical direction (m).

u = Average windspeed at the effective release height (H), (m/s).

L = Inversion layer height (m).

Atmospheric Stability Classification

Meteorologists distinguish several states of the atmospheric surface layer—unstable, neutral, and stable. These categories refer to how a parcel of air reacts when displaced adiabatically in the vertical direction. HOTSPOT allows you to select the atmospheric stability classification in two ways.

For those not familiar with the different stability classifications, HOTSPOT will select the appropriate stability classification based on user-input of direct observations. Or, users can directly select and force a particular stability classification. The simplified method requires selecting the solar insolation factor and the ground windspeed (2-m height). HOTSPOT automatically determines the atmospheric stability category from the matrix in the following table. This table contains criteria for the six stability classes, based on five categories of solar insolation. The scheme is widely used in meteorology and is accepted for stability class estimates.

| Meterological condition | ons that define Atm | ospheric Stability (| Categories, A–F, used |
|-------------------------|---------------------|----------------------|-----------------------|
| in HOTSPOT. | | | |
| | | | |

| <2 | А | В | F |
|-----|---|---|---|
| 2–3 | А | С | Е |
| 3–4 | В | С | D |
| 4–6 | С | D | D |
| >6 | С | D | D |

Pasquill Stability Types:

A: Extremely Unstable ($\sigma_e = 25 \text{ deg}$)

B: Moderately Unstable ($\sigma_{\rm e}$ = 20 deg)

C: Slightly Unstable ($\sigma_{\theta} = 15 \text{ deg}$)

D: Neutral ($\sigma_{\theta} = 10 \text{ deg}$)

E: Slightly stable $(\sigma_e = 5 \text{ deg})$

F: Moderately Stable (σ_{θ} = 2.5 deg)

Worst-Case Stability

For an elevated release, the location of the maximum concentration depends on the stability class chosen. For materials with a deposition velocity of zero and a release point at or very near GROUND LEVEL, the maximum concentration is always associated with "F" stability. However, if the deposition velocity is greater than zero, the worst-case stability at large downwind distances is not always associated with "F" stability due to the effects of plume depletion, i.e., the concentration of the plume decreases at a faster rate with increasing stability class (A-F) and increasing deposition velocity. For example, at a specific location, "E" stability could result in a higher local concentration than "F" due to LESS plume depletion associated with "E" stability. This effect is minimal for deposition velocities less than 0.1 cm/sec.

Special G Stability

Diffusion experiments under clear, nearly calm nighttime conditions suggest that horizontal diffusion is actually greater than diffusion F stability (i.e., larger σ_y) due to increased plume meander. The standard deviation of the observed wind fluctuations in the horizontal direction, σ_θ , can be very large. The observed σ_θ values during G stability conditions correspond to anything between categories A–F, i.e., diffusion in terms of tabulated dispersion parameters is indeterminate during G stability conditions (Hanna, 1982). The diffusion can best be estimated using the actual measurement of σ_θ . If the G stability class is selected, the user is prompted for σ_θ , and the applicable stability class used for the horizontal diffusion component. F stability is assumed for the vertical component.

Determining $\sigma_{\rm y}$ and $\sigma_{\rm z}$

The most widely used scheme to estimate σ_y and σ_z was developed by Pasquill (1961). Briggs (1975) combined the Pasquill curves with curves derived from data observed at Brookhaven National Laboratory and the Tennessee Valley Authority, the latter including observations out to a downwind distance of 10 km. Briggs incorporated theoretical concepts regarding asymptotic limits of the formulas to produce a widely used set of equations for σ_y and σ_z . The equations are associated with dispersion experiments conducted over short grassy surfaces with roughness lengths in the range from 0.01 m to 0.1 m. Briggs' formulas are applicable from a distance of 0.1 km to ~10 km and are can be extended to 20 or 30 km, although Briggs does not recommend this extension. However, for lack of any other validation schemes, these formulas are commonly used out to a distance of 100 km.

Equations used to determine σ_y and σ_z . This methodology is derived from Briggs (1975).

| Pasquill Type | $\sigma_{\!_{\!y}}(m)$ | $\sigma_{\!_{Z}}(m)$ |
|---------------|---|------------------------------------|
| А | $0.22 \mathrm{x} \; (1 + 0.0001 \mathrm{x})^{-1/2}$ | 0.20x |
| В | $0.16x (1+0.0001x)^{-1/2}$ | 0.12x |
| С | 0.11x (1+0.0001x) ^{-1/2} | 0.080x (1+0.0002x) ^{-1/2} |
| D | $0.08x (1+0.0001x)^{-1/2}$ | $0.060x (1+0.0015x)^{-1/2}$ |
| Е | $0.06x (1+0.0001x)^{-1/2}$ | 0.030x (1+0.0003x) ⁻¹ |
| F | $0.04 \mathrm{x} \; (1 + 0.0001 \mathrm{x})^{-1/2}$ | 0.016x (1+0.0003x) ⁻¹ |

Sample Time

The equations for the standard deviation of the Gaussian concentration distribution in cross-axis direction (σ_y) are representative of observing plume characteristics over a time period of 10 min. In the HOTSPOT codes, this averaging time is referred to as the sampling time. Concentrations downwind from a source decrease with increasing sampling time primarily because of a larger σ_y due to an increased meander of wind direction. In the HOTSPOT codes, the default release duration of radioactive material is 10 min. If you are interested in a scenario with a release duration of 1 hour, you need to change the sample time to 60 min. The sample time for the explosive-release programs is fixed at 10 min and cannot be altered. However, the sample time may be changed in non-explosive programs at the main HOTSPOT output menu using the "T: SAMPLE TIME" option. In HOTSPOT, the following equation adjusts for sampling times different than 10 min (Hanna, *et al.*, 1982; Gifford, 1975)—

$$\sigma'_{y} = \sigma_{y} \left[\frac{t}{10} \right]^{0.2} , \qquad (Eq. B-3)$$

where-

 σ_y = 10-min standard deviation of the concentration distribution. σ_y = Standard deviation for averaging time, t.

Effective Release Height

The actual plume height may not be the physical stack height. Plume rise can occur because of the velocity of stack emission, and the temperature differential between the stack effluent and the surrounding air. The rise of the plume results in an increase in the release height.

This effective release height leads to lower integrated concentrations at ground level. If you cannot estimate or calculate the effective release height, the actual physical release height (height of the stack) or zero for ground-level release should be used. This will always yield a conservative estimate, i.e., larger radiation doses, etc.

Wind Speed Variation with Height

The wind speed that users input is the estimate for a height of 2 m. However, the Gaussian plume equation requires the wind speed at H, the effective release height. HOTSPOT automatically uses the following power-law formula to determine the wind speed for all effective heights greater than 2 m.

$$u(H) = u(2) \left[\frac{H}{2} \right]^P$$
, (Eq. B-4)

where—

u(2) = Surface wind speed (m/s) at 2-m height.

 H_{eff} = Effective release height (m). = Factor from the following table.

Exponential factor used by HOTSPOT for calculating wind speed variation with height (from Hanna, 1982).

| Stability Class | | | | | |
|-----------------|------|------|------|------|------|
| A B C D E F | | | | | |
| 0.07 | 0.07 | 0.10 | 0.15 | 0.35 | 0.55 |

page A-5 February 9, 1995

Plume Depletion

Very small particles and gases or vapors are deposited on surfaces as a result of turbulent diffusion and Brownian motion. Chemical reactions, impaction, and other biological, chemical, and physical processes combine to keep the released substance at ground level. As this material is deposited on the ground, the plume above becomes depleted. HOTSPOT uses a source-depletion algorithm to adjust the air concentration in the plume to account for this removal of material.


The source term in HOTSPOT is allowed to decrease with downwind distance. The code accomplishes this by multiplying the original source term by a source-depletion factor [DF(x)]. The evaluation of this depletion factor has been described by Van der Hoven (in Slade, 1986).

The equation used in HOTSPOT is—
$$DF(x) = \left[\exp \int_{0}^{x} \frac{1}{\sigma_{z}(x) \exp\left[\frac{1}{2} \left(\frac{H_{eff}}{\sigma_{z}(x)}\right)^{2}\right]} dx \right]$$
(Eq. B-5)

Plume Rise

The actual plume height may not be the physical release height (the stack height). Plume rise can occur because of the velocity of the stack emission, and the temperature differential between the stack effluent and the surrounding air. The rise of the plume results in an increase in the release height, as shown in Fig. B-2.

This effective increase in release height leads to lower concentrations at the ground level. If you cannot visually estimate or calculate the effective release height, we recommend you use the actual physical release height (the height of the stack) or use zero height for a ground-level release. This will almost always yield conservative estimates.



Fuel Fire

In the specific case of a fuel fire (e.g., an aircraft accident involving burning fuel), you have the option of having HOTSPOT calculate buoyant plume rise. The momentum plume rise for a fire in open terrain is minimal compared to the buoyancy rise and the former is assumed to be zero (Fig. B-3). Two important parameters in the determination of plume rise are the heat emission rate (Q_H) and the buoyancy flux (F_P) . For a fuel fire, the heat emission rate is—

$$Q_H = 3785 \ V \rho H_C (1-f)/t$$
, (Eq. B-6)

where-

 Q_H = Heat emission rate (cal/s).

3785 = Volume conversion factor (cm³/gal). V = Volume of fuel (gal) burned in time, t (s).


 ρ = Fuel density (g/cm³).

 H_C = Heat of combustion (cal/g).

f = Fraction of the heat of combustion radiated.

t = Duration of fuel fire (s).

Note: The volume of fuel consumed in time *t* determines the buoyant plume rise. The default duration of the radioactive material release is 10 min, regardless of the duration of the fire. The default 10-min value can be changed using the "T: SAMPLE TIME" option at the main HOTSPOT output menu (see *Sample Time* in Appendix C). Experiments have shown that burn rates, given in terms of pool depth rate, generally fall within the range of 1–5 mm per minute (Drysdale, 1985).



 σ_y (x = 0) = σ_z (x = 0) = Maximum (0.5 R_{plume} or 0.5 R_{fire})

Fire Model Geometry

18-S/1207-B-3

In HOTSPOT, it is assumed that 30% of the heat of combustion is radiated, fuel density is 0.81 g/cm³, and the heat of combustion is 1.2×10^4 cal/g. Therefore, Eq. B-6 becomes—

$$Q_H = 2.58 \times 10^7 \, V/t$$
 (Eq. B-7)

Given the heat emission rate, the buoyancy flux is—

$$F_B = gQ_H / \pi C_p \rho_a T_a$$
 , $\left(m^4 / s^3 \right)$ (Eq. B-8)

where—

= Gravitational acceleration (9.8 m/s^2).

 C_p = Specific heat of effluent gases (0.24 cal/[g°K]). ρ_a = Density of air (1.29 × 10³ g/m³). T_a = Ambient air temperature (°K).

Therefore,

$$F_B = 1.1 \times 10^{-2} \, Q_H / T_a$$
.

The effective release height due to buoyancy plume rise is determined as follows (Briggs, 1975):

• For atmospheric stability classifications A, B, C, and D,

$$H_{eff} = 1.6 (F_B)^{1/3} (X^*)^{2/3} / u (H_{eff}/2)$$
 (Eq. B-9)

where—

 H_{eff} = Effective release height (m)

 X^* = Distance associated with final plume height (m) [Munger, 1982]

 $X^* = 119 (F_B)^{0.40} \text{ for } F_B \ge 55.$ $X^* = 49 (F_B)^{0.625} \text{ for } F_B > 55.$

• For stability classifications E and F,

for
$$u(H_{eff}/2) > 1.4 \text{ m/s}$$
,

$$H_{eff} = 2.6 \left(\frac{F_B}{\mu(2) \times S} \right)^{1/3};$$
 (Eq. B-10)

for
$$u(H_{eff}/2) \leq 1.4 \text{ m/s}$$
,

$$H_{eff} = 5.0 (F_B)^{1/4} (S)^{-3/8};$$
 (Eq. B-11)

where—

 $S = 0.020 \text{ g/} T_a \text{ for stability class E.}$ $S = 0.035 \text{ g/} T_a \text{ for stability class F.}$

page A-8 February 9, 1995

Briggs' plume-rise equations apply to the release from a stack with a negligible radius. The plume rise from a burning pool of fuel will be less than the Briggs value. For a burning pool of radius (*R*), the calculated plume rise is modified as follows (Mills, 1987):

$$H_{eff} = \sqrt[3]{\left(H_B\right)^3 + \left(\frac{R}{\gamma}\right)^3} - \frac{R}{\gamma} , \qquad (Eq. B-12)$$

where-

 H_R = Effective release height via the Briggs methodology (m).

R = Radius of burning fuel pool (m).

 γ = Entrainment coefficient for buoyant plume rise, 0.6.


Once the effective release height is determined, the radius of the final bent-over plume is set equal to 60% of the effective release height (Hanna, et al. 1982). An upwind virtual-term point source is used to model the initial distribution of material. The virtual-term point spurce is positioned at an up-wind distance, resulting in a σ_v and σ_z , above the origin, equal to 50% of the final bent-over plume radius. If the input pool radius is larger than the calculated plume radius, the actual pool radius is used for the target σ_v and σ_z values.

Explosion

The release fraction is partitioned as follows (Fig. B-4, following page):

Five separate source terms model the above initial distribution of material. The sources are represented by separate elevated upwind virtual source terms in which each term results in:

- $\sigma_{\rm v}$ over the explosion point equal to 50% of the cloud radius defined above.
- σ_z over the explosion point equal to 20% of the cloud top.



Cloud radius = 0.2 cloud top

 $\sigma_z (x = 0) = 0.2$ Cloud top

Where w = pounds of high explosives (Church, 1969)

Source distribution

20% ($h_5 = 0.8$ cloud top)

35% ($h_4 = 0.6$ cloud top)

25% ($h_3 = 0.4$ cloud top)

16% $(h_2 = 0.2 \text{ cloud top})$

4% $(h_1 = ground level)$

Explosion Model Geometry

18-S/1207-B-4

Resuspension


An upwind virtual source term models the initial distribution of material. The virtual-term point source is positioned at an upwind distance that results in a σ_{v} , at the center of the contamination zone, equal to 50% of the input effective radius (Fig. B-5).

The resuspension factor (*S*) for windspeed (*u*) at or below 3 m/s (Anspaugh, 1975):

$$S = 10^{-4} e^{-0.15 \sqrt{t}} + 10^{-9}$$
 m⁻¹, (Eq. B-13)

where t = time since contamination event (days).

page A-10 February 9, 1995



$$\sigma_{z}\left(x=0\right)=0$$

Resuspension Model Geometry

18-S/1207-B-5

Resuspension as a factor of wind speed:

$$S(u) = S \times (u/3)^2$$
 for $u > 3$ m/s
 $S(u) = S$ for $u \le 3$ m/s (Eq. B-14)

The effective source term (Q_{eff}) associated with the observed ground contamination (G) is—

$$Q_{eff} = S(u) \times G \times \pi \times \sigma_{y,origin} \times \sigma_{z,origin} \times u \quad , \quad \text{Ci/sec}$$
 (Eq. B-15)

where $G = \text{ground contamination } (\text{Ci/m}^2).$

The Gaussian standard deviations are evaluated at a distance equal to the distance from the origin to the upwind virtual source position. $Q_{\rm eff}$ can then be used in the Gaussian equation (see Appendix B) to estimate the radionuclide concentration downwind from the contamination.

Notes: The resuspension factor is determined using measurements of the ground contamination (Ci/m²), and the radionuclide air concentration (Ci/m³) above the ground measurement location. The resuspension factor is then defined as the ratio of the air concentration to the ground concentration (m⁻¹).


The 50-year committed effective dose equivalents are calculated per one-hour residence time. Therefore, an individual would be committed to the output dose for each one hour at the output location. The sampling time associated with resuspension is automatically changed from the normal 10-min values to 60-min values. The calculated resuspension factor is based on experimental data associated with the Nevada Test Site, and are not necessarily applicable to wet regions, etc. However, the above equations will result in a conservative resuspensionfactor estimate for an initial hazard evaluation. Once the resuspension factor is actually determined via air sampling, the new factor can update the original downwind predictions.

page A-11 February 9, 1995

Particle-Size Distribution

The particle size of a monodisperse suspension of fine solid or liquid particles in the atmosphere is completely characterized by the particle diameter. However, most aerosols are polydisperse and the particle sizes range over many magnitudes. In the HOTSPOT dispersion models, we are specifically concerned with the particle-size distribution with respect to radioactivity. Just as a number distribution gives the fraction of the total number of particles in any size range, the activity distribution gives the fraction of the total activity associated with the particles in any size range.

In most polydisperse aerosols, the normal distribution function does a poor job of representing the particle-size distribution. However, the logarithm of the particle size is adequately represented by a normal distribution. Hence, the log normal distribution is commonly used to statistically describe polydisperse particle-size distributions. In the HOTSPOT programs, it is assumed that the activity median aerodynamic diameter (AMAD) is 1 μm (geometric standard deviation is 3). The following figure represents the cumulative activity distribution for a log normal distribution with an AMAD of 1 μm . Note that 50% of the activity is associated with particles with an aerodynamic diameter less than 1 μm , and essentially all of the "respirable" activity is below particles with an aerodynamic diameter of approximately 10 μm . The default ICRP-30 internal dosimetry conversion factors also assume a 1- μm AMAD particle-size distribution. In many models and studies, the respirable fraction is commonly defined as "all the material with an aerodynamic diameter less than 10 micrometers." As shown in the following graph, the 1- μm AMAD agrees with this assumption (Fig. B-6).



Stating the distribution in terms of aerodynamic diameter standardizes the distribution in both particle shape and density. The aerodynamic diameter is the diameter of a unit density (1 g/cm³) sphere that has the same settling velocity as the actual particle. If a particle has an aerodynamic diameter of 1 μm , it behaves in an aerodynamic sense like a 1- μm water droplet regardless of the particle's shape, density, or physical size.

Technical Information Department • Lawrence Livermore National Laboratory University of California • Livermore, California 94551